

# **Synopsys® Common Licensing Administration Guide**

---

Version 11.1, December 2009

**SYNOPSYS®**

# Copyright Notice and Proprietary Information

Copyright © 2009 Synopsys, Inc. All rights reserved. This software and documentation contain confidential and proprietary information that is the property of Synopsys, Inc. The software and documentation are furnished under a license agreement and may be used or copied only in accordance with the terms of the license agreement. No part of the software and documentation may be reproduced, transmitted, or translated, in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without prior written permission of Synopsys, Inc., or as expressly provided by the license agreement.

## Right to Copy Documentation

The license agreement with Synopsys permits licensee to make copies of the documentation for its internal use only. Each copy shall include all copyrights, trademarks, service marks, and proprietary rights notices, if any. Licensee must assign sequential numbers to all copies. These copies shall contain the following legend on the cover page:

“This document is duplicated with the permission of Synopsys, Inc., for the exclusive use of \_\_\_\_\_ and its employees. This is copy number \_\_\_\_\_.”

## Destination Control Statement

All technical data contained in this publication is subject to the export control laws of the United States of America. Disclosure to nationals of other countries contrary to United States law is prohibited. It is the reader's responsibility to determine the applicable regulations and to comply with them.

## Disclaimer

SYNOPSYS, INC., AND ITS LICENSORS MAKE NO WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, WITH REGARD TO THIS MATERIAL, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

## Registered Trademarks (®)

Synopsys, AMPS, Astro, Behavior Extracting Synthesis Technology, Cadabra, CATS, Certify, CHIPit, Design Compiler, DesignWare, Formality, HDL Analyst, HSIM, HSPICE, Identify, Leda, MAST, ModelTools, NanoSim, OpenVera, PathMill, Physical Compiler, PrimeTime, SCOPE, Simply Better Results, SiVL, SNUG, SolvNet, Syndicated, Synplicity, Synplify, Synplify Pro, Synthesis Constraints Optimization Environment, TetraMAX, the Synplicity logo, UMRBus, VCS, Vera, and YIELDirector are registered trademarks of Synopsys, Inc.

## Trademarks (™)

AFGen, Apollo, Astro-Rail, Astro-Xtalk, Aurora, AvanWaves, BEST, Columbia, Columbia-CE, Confirma, Cosmos, CosmosLE, CosmosScope, CRITIC, CustomExplorer, CustomSim, DC Expert, DC Professional, DC Ultra, Design Analyzer, Design Vision, DesignerHDL, DesignPower, DFTMAX, Direct Silicon Access, Discovery, Eclipse, Encore, EPIC, Galaxy, Galaxy Custom Designer, HANEX, HAPS, HapsTrak, HDL Compiler, Hercules, Hierarchical Optimization Technology, High-performance ASIC Prototyping System, HSIM<sup>plus</sup>, i-Virtual Stepper, IICE, in-Sync, iN-Tandem, Jupiter, Jupiter-DP, JupiterXT, JupiterXT-ASIC, Liberty, Libra-Passport, Library Compiler, Magellan, Mars, Mars-Rail, Mars-Xtalk, Milkyway, ModelSource, Module Compiler, MultiPoint, Physical Analyst, Planet, Planet-PL, Polaris, Power Compiler, Raphael, Saturn, Scirocco, Scirocco-i, Star-RCXT, Star-SimXT, StarRC, System Compiler, System Designer, Taurus, TotalRecall, TSUPREM-4, VCS Express, VCSi, VHDL Compiler, VirSim, and VMC are trademarks of Synopsys, Inc.

## Service Marks (SM)

MAP-in, SVP Café, and TAP-in are service marks of Synopsys, Inc.

SystemC is a trademark of the Open SystemC Initiative and is used under license.

ARM and AMBA are registered trademarks of ARM Limited.

Saber is a registered trademark of SabreMark Limited Partnership and is used under license.

All other product or company names may be trademarks of their respective owners.

# Contents

---

What's New in This Release . . . . .	x
About This Guide . . . . .	x
Customer Support. . . . .	xiii
<b>1. Introduction</b>	
Overview of Synopsys Common Licensing (SCL) Version 11.1 . . . . .	1-2
Summary of Tasks to Set Up SCL . . . . .	1-3
Supported Platforms. . . . .	1-3
Synopsys Legacy Vendor Daemons. . . . .	1-5
<b>2. Migrating to Synopsys Common Licensing</b>	
Planning Your Migration . . . . .	2-2
License Pooling Functionality . . . . .	2-2
Rollover Functionality. . . . .	2-2
Hardware, Operating System, and Other Requirements . . . . .	2-3
Platform Requirements . . . . .	2-3
Hosting a Server With Other Vendor Daemons. . . . .	2-4
Single Server Configuration. . . . .	2-4
Socket Descriptor Limit . . . . .	2-5
TCP and Network Settings . . . . .	2-5
WAN License Servers . . . . .	2-5
Compute Farm and License Server. . . . .	2-6
Network Mounted File System . . . . .	2-6

Options File Use Guidelines . . . . .	2-6
Requirements for Starting the SCL Server . . . . .	2-7
Legacy Application Compatibility With SCL . . . . .	2-8
<b>3. Before You Install Synopsys Common Licensing Software</b>	
Checking the Integrity of the License File . . . . .	3-2
Using sssverify . . . . .	3-2
Mapping Features to Products . . . . .	3-2
License Server Configurations . . . . .	3-3
Single Server . . . . .	3-3
Multiple Single License Servers . . . . .	3-4
Three-Server Redundancy . . . . .	3-4
License Server Configurations Summary . . . . .	3-5
Selecting Host Nodes to Be Used As Servers . . . . .	3-6
Standard FLEXnet License File List Behavior . . . . .	3-6
Rollover Behavior When Server Goes Offline . . . . .	3-7
<b>4. Downloading SCL Software and Obtaining License Key Files</b>	
Registering for SolvNet and Downloading SCL . . . . .	4-2
Obtaining the Synopsys License Key File . . . . .	4-2
About the License Key File . . . . .	4-2
Logging In to SmartKeys . . . . .	4-3
Retrieving Term Licenses . . . . .	4-3
Retrieving Monthly Technology Subscription Licenses . . . . .	4-4
<b>5. Configuring and Verifying the License Key File</b>	
Viewing the SCL Licensing Installation Directory Structure . . . . .	5-2
Verifying the License Key File . . . . .	5-5
Verifying the License Key File Host ID . . . . .	5-5
Checking the License Key File for Errors . . . . .	5-6
Avoiding License Key File Errors . . . . .	5-6
Placing the License Key File on Your System . . . . .	5-7
Required License Key File Modifications . . . . .	5-7
Modifying SERVER Line Data Items . . . . .	5-8

Modifying VENDOR Line Data Items . . . . .	5-8
Locating and Using the Options File . . . . .	5-10
<b>6. Starting the SCL Server on UNIX and Windows Systems</b>	
Starting the SCL License Server Daemon . . . . .	6-2
Starting the License Server on One or More Servers . . . . .	6-2
Using the Imgrd Command to Start SCL . . . . .	6-2
Specifying a Debug Log File . . . . .	6-3
Describing the License Environment Variables . . . . .	6-4
About Environment Variables . . . . .	6-5
Specifying Values for License Software Environment Variables . . . . .	6-5
Using port@host Notation . . . . .	6-6
Using Environment Variables to Configure Clients for Multiple-Server Access . . . . .	6-7
Using Environment Variables to Configure Clients for Three-Server Redundancy . . . . .	6-7
Using the Imdown Command to Stop SCL . . . . .	6-8
<b>7. Explaining the License Key File</b>	
About the License Key File . . . . .	7-2
The License Key File Header . . . . .	7-2
License Key File Comment Lines . . . . .	7-3
The SERVER Line . . . . .	7-3
The VENDOR Line . . . . .	7-4
The USE_SERVER Line . . . . .	7-5
The License Key File INCREMENT Line . . . . .	7-6
On-Support Keys . . . . .	7-8
SUPERSEDE Keys . . . . .	7-8
Synopsys Example License File . . . . .	7-9
<b>8. Maintaining Synopsys Common Licensing</b>	
Maintaining Synopsys Common Licensing . . . . .	8-2
SCL License Key File Verification Checklist . . . . .	8-2

Validating New SCL Key Files . . . . .	8-3
Validating Existing or New SCL License Files . . . . .	8-3
Procedure to Update a Synopsys License File . . . . .	8-4
License Expiration Alert . . . . .	8-6
SCL_DISPLAY_EXPIRE . . . . .	8-6
SCL_DAYS_EXPIRE . . . . .	8-6
<b>9. Identifying and Resolving Problems</b>	
Common Problems . . . . .	9-2
Determining Why You Cannot Start the Server . . . . .	9-2
Diagnosing Why You Cannot Check Out a License . . . . .	9-3
Mapping SCL Error Messages to FLEXnet Error Codes . . . . .	9-4
Error Conditions: Possible Causes and Solutions. . . . .	9-7
Causes. . . . .	9-7
Solutions . . . . .	9-8
Troubleshooting . . . . .	9-9
Determining Your Host ID by Using Imhostid. . . . .	9-9
Using sssverify to Troubleshoot a Synopsys License File . . . . .	9-10
Determining Whether Your Tool Is Enabled for SCL . . . . .	9-14
Finding the Physical Location of the License File . . . . .	9-14
Finding a List of All Tools Users. . . . .	9-15
Checking the Daemon Versions for Compatibility . . . . .	9-15
System Monitoring Script . . . . .	9-15
Using the Debug Log File to Troubleshoot License Issues . . . . .	9-17
Common Error Messages Reported in the Debug Log File . . . . .	9-18
SSS-Related Errors . . . . .	9-18
Other Messages and Resolutions. . . . .	9-19
Filtering Information From the Server Log File . . . . .	9-21
Building and Running watchlog.c . . . . .	9-21
What Happens When the License Server Goes Down. . . . .	9-23
Verifying the Content and Integrity of the License Key File . . . . .	9-23
Checking Requisite License Key File Content: SERVER and VENDOR Lines . . . . .	9-23
Checking the Host ID . . . . .	9-23

Using Imdiag and Imstat to Diagnose Problems When You Cannot Check Out a License .....	9-24
Diagnosing Problems With FLEXnet .....	9-26
Known Issues .....	9-26
Licensing Checkout (Heartbeat) Errors .....	9-26
Minimizing Heartbeat Failures .....	9-26
Tools Based on Legacy Daemons Fail to Start .....	9-27
Legacy Applications Issue With License Pooling of Multiple Key Files .....	9-28
SCL License Server Out-of-File Descriptors on Linux Operating Systems .....	9-29
Imgrd Error Message: Failed to open the TCP port number in the license .....	9-29
SCL Crashes With Errors in the Debug Log File .....	9-30

## Appendix A. Starting SCL on Windows Platforms With LMTOOLS

General Information and Installation .....	A-2
SCL Components .....	A-2
Starting SCL Automatically With LMTOOLS .....	A-2
Ordering FLEXnet Dongles and Installing Dongle Drivers .....	A-4
Ordering a FLEXnet Dongle for Synopsys Tools .....	A-4
Installing Dongle Drivers on Windows Systems .....	A-5
Node-Locked Uncounted and Counted Licenses .....	A-6
Uncounted Node-Locked License Keys .....	A-6
Counted node-locked license keys .....	A-6
Troubleshooting Dongle Problems .....	A-7
Troubleshooting SCL Startup Problems .....	A-8
SCL Service fails to Start Automatically on Windows Platforms .....	A-8
Errors in the Debug Log File .....	A-9
Troubleshooting Tool Startup Problems .....	A-10
General Troubleshooting .....	A-10
Troubleshooting Firewall Problems .....	A-10
The FLEXnet License Finder Dialog Box .....	A-11

## Appendix B. SCL Command-Line Interface

Getting Help on Commands .....	B-2
Listing Commands .....	B-2

Getting Command Usage Help . . . . .	B-2
Syntax . . . . .	B-2
Example . . . . .	B-2
Abbreviating Commands and Options . . . . .	B-3
Arguments . . . . .	B-3
Comment Character . . . . .	B-3
Validating a License Key on the License Server . . . . .	B-3
Testing the License Server for Performance . . . . .	B-4
Commands to Validate the Socket Connection Limit . . . . .	B-4
Commands to Stress Test the License Server With Multiple License Requests . . . . .	B-5
<b>Appendix C. SCL License Key File Sort Utility</b>	
Features . . . . .	C-2
Usage . . . . .	C-3
Examples . . . . .	C-4
Using a Feature Name in Descending Order . . . . .	C-4
Using the Expiration Date in Descending Order . . . . .	C-5
Using the Key Name in Ascending Order and the Start Date in Descending Order . . . . .	C-6
<b>Index</b>	

# Preface

---

This preface includes the following sections:

- [What's New in This Release](#)
- [About This Guide](#)
- [Customer Support](#)

---

## What's New in This Release

Information about new features, enhancements, and changes; known problems and limitations; and resolved Synopsys Technical Action Requests (STARs) is available in the *Synopsys Common Licensing Release Notes* in SolvNet.

To see the *Synopsys Common Licensing Release Notes*,

1. Go to the Download Center on SolvNet located at the following address:

<https://solvnet.synopsys.com/DownloadCenter>

If prompted, enter your user name and password. If you do not have a Synopsys user name and password, follow the instructions to register with SolvNet.

2. Select Synopsys Common Licensing, and then select a release in the list that appears.

---

## About This Guide

This guide provides information about Synopsys Common Licensing (SCL) 11.1. It describes how to maintain the licensing software and provides troubleshooting guidelines.

Note:

Install a single copy of SCL on your license server to be used with all Synopsys tools. Installation of Synopsys tools and SCL is not order dependent. That is, you can install SCL before or after you install your Synopsys tools. However, you cannot use any Synopsys tools reliant on SCL until you have installed and configured SCL.

---

## Audience

The *Synopsys Common Licensing Administration Guide* is intended for the license network administrator responsible for installing and maintaining the SCL software. Client users of Synopsys tools who set their own licensing environment variables will also find this guide useful.

To use this guide, experience installing Synopsys tools is helpful, including setting environment variables for the client systems on which you run those tools. Though not a requirement, familiarity with the Flexera Software FLEXnet product will facilitate your SCL installation, configuration, and administration.

---

## Related Publications

For additional information about Synopsys Common Licensing, see Documentation on the Web, which is available through SolvNet at the following address:

<https://solvnet.synopsys.com/DocsOnWeb>

You can also refer to the following documentation:

- *Synopsys Installation Guide*

This guide is available at <http://www.synopsys.com/install>

- *FLEXnet Licensing End Users Guide*

The *FLEXnet Licensing End Users Guide* is available from Synopsys at <http://www.synopsys.com/Support/Licensing/Licensing/Documents/Dockkeys/enduser.pdf>. It is also delivered with the SCL software.

SCL runs on various platforms. For information about supported platforms, operating systems, and keywords, see the *Synopsys Common Licensing Release Notes* in SolvNet or the Synopsys Licensing QuickStart Web page at <http://www.synopsys.com/Support/Licensing/Licensing/Pages/SupportedOS.aspx>.

- SolvNet articles pertaining to SCL

See “[Accessing SolvNet](#)” on page xiii.

The *Synopsys Common Licensing Administration Guide* version 11.1 is available in PDF format in the SCL installation directory at `scl_root/doc/SCL_11.1_Administration_Guide.pdf`.

---

## Conventions

The following conventions are used in Synopsys documentation.

Convention	Description
Courier	Indicates command syntax.
<i>Courier italic</i>	Indicates a user-defined value in Synopsys syntax, such as <i>object_name</i> . (A user-defined value that is not Synopsys syntax, such as a user-defined value in a Verilog or VHDL statement, is indicated by regular text font italic.)
<b>Courier bold</b>	Indicates user input—text you type verbatim—in Synopsys syntax and examples. (User input that is not Synopsys syntax, such as a user name or password you enter in a GUI, is indicated by regular text font bold.)
[ ]	Denotes optional parameters, such as <i>pin1 [pin2 ... pinN]</i>
	Indicates a choice among alternatives, such as <i>low   medium   high</i> (This example indicates that you can enter one of three possible values for an option: low, medium, or high.)
–	Connects terms that are read as a single term by the system, such as <i>set_annotated_delay</i>
Control-c	Indicates a keyboard combination, such as holding down the Control key and pressing c.
\	Indicates a continuation of a command line.
/	Indicates levels of directory structure.
Edit > Copy	Indicates a path to a menu command, such as opening the Edit menu and choosing Copy.

---

---

## Customer Support

Customer support is available through SolvNet online customer support and through contacting the Synopsys Technical Support Center.

---

### Accessing SolvNet

SolvNet includes an electronic knowledge base of technical articles and answers to frequently asked questions about Synopsys tools. SolvNet also gives you access to a wide range of Synopsys online services including software downloads, documentation on the Web, and “Enter a Call to the Support Center.”

To access SolvNet, go to the SolvNet Web page at the following address:

<https://solvnet.synopsys.com>

If prompted, enter your user name and password. If you do not have a Synopsys user name and password, follow the instructions to register with SolvNet.

If you need help using SolvNet, click HELP in the top-right menu bar or in the footer.

---

### Contacting the Synopsys Technical Support Center

If you have problems, questions, or suggestions, you can contact the Synopsys Technical Support Center in the following ways:

- Open a call to your local support center from the Web by going to <https://solvnet.synopsys.com>, entering your user name and password and then clicking “Enter a Call to the Support Center.”
- Send an e-mail message to your local support center.
  - E-mail [support\\_center@synopsys.com](mailto:support_center@synopsys.com) from within North America.
  - Find other local support center e-mail addresses at <http://www.synopsys.com/Support/GlobalSupportCenters/Pages>
- Telephone your local support center.
  - Call (800) 245-8005 from within the continental United States.
  - Call (650) 584-4200 from Canada.
  - Find other local support center telephone numbers at <http://www.synopsys.com/Support/GlobalSupportCenters/Pages>



# 1

## Introduction

---

This chapter introduces Synopsys Common Licensing (SCL). It gives an overview of SCL 11.1, which is based on FLEXnet 11.6.1.6, the standard licensing software provided by Flexera Software (formerly Acresto Software).

In addition, this chapter describes the supported platforms and SCL features, including on-support licenses.

The following sections are included:

- [Overview of Synopsys Common Licensing \(SCL\) Version 11.1](#)
- [Summary of Tasks to Set Up SCL](#)
- [Supported Platforms](#)
- [Synopsys Legacy Vendor Daemons](#)

---

## Overview of Synopsys Common Licensing (SCL) Version 11.1

Synopsys Common Licensing (SCL) provides a single method of obtaining licenses used by all Synopsys tools. SCL reduces licensing administration complexity, minimizing the effort you expend in installing, maintaining, and managing licensing software for Synopsys tools.

SCL version 11.1 is based on combined vendor daemon technology from Flexera Software, formerly Acresto Software, which is based on the FLEXnet (formerly FLEXlm) 11.6.1.6 release. This technology provides the capability to run a single vendor daemon, `snpslmd`, to serve licenses to all Synopsys products. The SCL 11.1 `snpslmd` vendor daemon replaces all previously released Synopsys vendor daemons. For a complete list of legacy vendor daemons, see [“Synopsys Legacy Vendor Daemons” on page 1-5](#).

The FLEXnet `lmgrd` license daemon manages the initial interaction with the client application requesting a license. The `lmgrd` daemon also locates and starts the `snpslmd` daemon, passing to it the connection with the client application. The `snpslmd` daemon reads and interprets (parses) the license key file and then handles client license requests.

The Synopsys `snpslmd` vendor daemon maintains the usage counts for Synopsys licensed tools. In addition to standard FLEXnet vendor daemon functionality, `snpslmd` also implements functionality that is specific to Synopsys to support features such as on-support licensing on the server.

### Important:

You must use FLEXnet 11.6.1 or a later version of the `lmgrd` license daemon.

SCL 11.1 includes the following features.

- It uses the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` license environment variable.
- It is delivered as a standalone tool. That is, it is available as a separate download or on a separate CD. Therefore you need to install only one copy of SCL for all of your Synopsys tools.

In addition, SCL 11.1 provides on-support licensing. On-support licenses

- Are provided when you purchase maintenance for a product.
- Allow for ongoing availability of the licensed feature as new versions of the feature become available.
- Provide continuous support for a tool until the expiration date of the license. Generally, support continues for versions released up to two years after the version specified in the license key file.

For details about on-support licenses, including an example of an on-support license key, see [“On-Support Keys” on page 7-8](#).

---

## Summary of Tasks to Set Up SCL

To use licensed Synopsys tools, you must

- Obtain and install the SCL 11.1 software.
- Download and configure the license key file for your site.
- Start SCL by using the provided `lmgrd` license server daemon.
- Set environment variables on client systems to specify the location of the SCL license key file which specifies the location of the SCL `snpslmd` vendor daemon.

This guide covers these tasks in the chapters that follow, with the exception of SCL 11.1 installation. For instructions on installing SCL, see the Synopsys Installation Guide at

<http://www.synopsys.com/Support/Licensing/Installation/Pages/default.aspx>

---

## Supported Platforms

SCL runs on various OS platforms. For information about supported platforms, operating systems, and keywords for the SCL server, see [Table 1-1](#) or the *Synopsys Common Licensing Release Notes* in SolvNet.

SCL is platform-independent. This means that you can run any combination of SCL clients and servers, providing the client platform is supported by the Synopsys tools. Each client requires network access to a server through the Transmission Control Protocol (TCP).

For a list of platforms supported by SCL, see [Table 1-1](#), which shows a list of supported platforms.

*Table 1-1 Supported Platforms, Operating Systems, and License Daemons in SCL 11.1*

Platform	Keyword	Support for sandwork	Support for pdld	Support for synplctyd	All other Synopsys license daemons <sup>1</sup>
Red Hat Enterprise Linux x86 — 32-bit	linux	Yes	Yes	Yes	Yes
Red Hat Enterprise Linux x86-64 — 64-bit	amd64	Yes	Yes	Yes	Yes
SUSE Linux Enterprise Server — 32-bit	suse32	Yes	Yes	Yes	Yes

**Table 1-1 Supported Platforms, Operating Systems, and License Daemons in SCL 11.1**

Platform	Keyword	Support for sandwork	Support for pdld	Support for synplctyd	All other Synopsys license daemons <sup>1</sup>
SUSE Linux Enterprise Server x86-64 — 64-bit	suse64	Yes	Yes	Yes	Yes
Sun Solaris x86 — 32-bit	x86sol32	No	No	No	Yes
Sun Solaris x86-64 — 64-bit	x86sol64	Yes	No	No	Yes
Microsoft Windows XP Professional — 32-bit	windows	Yes	Yes	Yes	Yes
Sun Solaris SPARC — 32-bit	sparcOS5	Yes	Yes	Yes	Yes
Sun Solaris SPARC — 64-bit	sparc64	Yes	Yes	No	Yes
IBM AIX RS6000 — 32-bit	rs6000	No	No	No	Yes
IBM AIX RS6000 — 64-bit	aix64	No	No	No	Yes

<sup>1</sup> All other Synopsys license daemons (excluding sandwork, pdld, and synplctyd): adalmd, anagram, avantd, chrysalisd, hscd, metasoftd, saber\_dmn, tmalld, innologd, ISE-TCADd, EPIC, everest, la\_damon, leda, ssilmd, synopsysd, vcsd, nassd, numeritchd, TE\_CATS, CADABRA, snpsOEM1, snpsOEM2, snpsOEM3, and sigmacd.

**Important:**

- For Synplicity tools on a Linux platform, if you have a dongle, you must install the 32-bit daemon. You can run the 32-bit daemon on a 64-bit OS.
- For Synplicity tools, if you are using a Sun Solaris SPARC 64-bit platform, you must use the Sun SPARC 32-bit version of the SCL version 11.1 daemon because Synplicity Combined Vendor Daemon keys are supported only on the 32-bit version. If you prefer, you can move to the Red Hat Enterprise Linux 64-bit x86 (amd64) platform by rehosting your license keys. In order to rehost keys, contact your Account Manager and execute a License Key Rehost Agreement.

---

## Synopsys Legacy Vendor Daemons

[Table 1-2](#) shows the legacy vendor daemons incorporated into SCL 11.1 . (Other vendor daemons are not supported. Tools based on such daemons are not compatible with SCL 11.1 .) Before starting SCL, these daemon processes must be shut down. See [“Using the Imgrd Command to Start SCL” on page 6-2](#).

*Table 1-2 Legacy Daemons Incorporated Into SCL 11.1*

<b>Acquired Company</b>	<b>Daemons</b>
Analog Design Automation	adalmd
Avant! Corporation	anagram, avantd, chrysalisd, hscd, metasoftd, saber_dmn, tmalld
Innologic Systems, Inc.	innologd
Integrated Systems Engineering	ISE-TCADD
Legacy and other daemons	EPIC, everest, la_damon, leda, ssilmd, synopsysd, vcsd
Nassda Corporation	nassd
Numerical Technologies	numeritchd, TE_CATS, CADABRA
Placeholder for future OEM partners	snpsOEM2, snpsOEM3
SIGMA-C	sigmacd
Zenpire Corporation	snpsOEM1
Sandwork Design	sandwork
CHIPit	pdlld
Synplicity <sup>1</sup>	synplctyd

*1 This daemon was added in the 11.1 release. It is supported in version 11.1 only.*



# 2

## Migrating to Synopsys Common Licensing

---

This chapter describes the steps that are required to migrate to Synopsys Common Licensing (SCL) 11.1. It includes the following sections:

- [Planning Your Migration](#)
- [Hardware, Operating System, and Other Requirements](#)
- [Requirements for Starting the SCL Server](#)
- [Legacy Application Compatibility With SCL](#)

---

## Planning Your Migration

Synopsys recommends that you maintain multiple single license servers to achieve fault tolerance. For example, you might split 2,000 licenses among two separate license servers, each running a separate license file. You must consider licensing pooling and rollover functionality when creating your server migration plans. Make sure your license server hardware meets SCL requirements. See [“Supported Platforms” on page 1-3](#).

---

### License Pooling Functionality

License pooling is the ability of an application to check out licenses from two or more servers at the same time and should not be confused with wide area network (WAN) functionality. Each server in the pool must be running the same version of SCL.

Also, applications that are capable of pooling will not pool between servers running different daemons, even if both servers are in the license search path. For example, assume that you currently pool licenses and use multiple license servers and one server is running the `snpslmd` daemon and the other server is running the legacy `avantd` daemon. In this case, if you change some but not all of the servers to the `snpslmd` vendor daemon, license pooling between servers on different daemons can no longer occur. The solution is to migrate all the licenses to the `snpslmd` daemon (combined vendor daemon license file format) or to ensure that all servers on the license file path are for `snpslmd` only.

**Note:**

Pooling is supported by most but not all Synopsys tools. For a complete list of tools that have pooling functionality contact the Synopsys Support Center at

<https://solvnet.synopsys.com/EnterACall>

---

### Rollover Functionality

Rollover functionality allows the application to check out the license from the next daemon in its search path (defined by `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE`) if the current connected daemon goes down. This should not be confused with license WAN or pooling functionalities.

Applications will not roll over between the `snpslmd` combined vendor daemon and a legacy Synopsys license daemon if the current (connected) daemon goes down, even if both servers are in the license search path.

**Note:**

After you have migrated to the `snpslmd` combined vendor daemon on all of your servers, this problem will not occur.

---

## Hardware, Operating System, and Other Requirements

The following requirements will ensure that your migration to the SCL `snpslmd` vendor daemon is successful.

- [Platform Requirements](#)
- [Hosting a Server With Other Vendor Daemons](#)
- [Single Server Configuration](#)
- [Socket Descriptor Limit](#)
- [TCP and Network Settings](#)
- [WAN License Servers](#)
- [Compute Farm and License Server](#)
- [Network Mounted File System](#)
- [Options File Use Guidelines](#)

---

### Platform Requirements

If you currently using a Solaris SPARC server as your license server and are satisfied with its performance as the license server, you do not need to make any changes. If you are a new Synopsys customer or are migrating a new license server, we recommend that you use an AMD or an Intel processor with the Red Hat Enterprise Linux version 4 or 5 operating system (OS). The SCL `amd64` platform binary supports both AMD and Intel `x86_64` processors. Other OS platforms are not recommended for hosting the license server. The following hardware platform is recommended:

- AMD or Intel `x86_64` hardware running Red Hat Enterprise Linux version 4 or 5
- A CPU speed of 2 GHz or better
- Dual or multiple CPU machine or multiple cores (This allows the `lmgrd` and the `snpslmd` processes to run on separate CPUs.)
- 4 GB of memory
- 1 Gbps Ethernet card and 1 Gbps or better network switch

If you are serving large license quantities (more than 300), make sure that you meet these requirements. In addition, do not host more than 2,000 licenses on a single machine or you might see license failures because of the load on the server machine.

**Note:**

Certain other OS platforms are supported; but they are recommended only if the number of licenses is small. For a list of supported platforms, see [Table 1-1 on page 1-3](#) or the *Synopsys Common Licensing Release Notes* in SolvNet.

<http://www.synopsys.com/Support/Licensing/Licensing/Pages/SupportedOS.aspx>

If you do not meet these requirements or plan to host the license server on any other OS platforms, contact the Synopsys Support Center at

<https://solvnet.synopsys.com/EnterACall>

---

## Hosting a Server With Other Vendor Daemons

It is recommend that you do not host a Synopsys license daemon on the same machine with other license daemons based on FLEXnet. If you must share the same machine with other daemons or processes, make sure that your license server meets the specifications for the hardware platform, including multiple CPUs or cores of 2 GHz or better, 4 GB memory, and a 1 GBps Ethernet card. See “[Platform Requirements](#)” on page 2-3.

---

## Single Server Configuration

A single license server configuration is strongly recommended over a redundant, triad server configuration. The SCL components are most robust when they are part of a single-server configuration. The redundant server configuration adds an additional load on the license servers, which can increase latency, eliminating any advantage of redundancy.

Rather than using a redundant server configuration, it is recommended that you host multiple single-server configurations. This ensures that if the connection to one of the daemons is broken, some licenses will still be available; whereas if a redundant configuration fails (loss of quorum), no licenses will be available.

**Important:**

If you are serving a large quantity of licenses, make sure you do not allow more than 2,000 socket connections to a single SCL license server. (In general, a license checkout will consume one socket connection.) If you go over this limit, you might experience degradation in performance or license failures due to the load on the server. In this case, it is recommended that you divide licenses among multiple single license servers.

---

## Socket Descriptor Limit

Set the socket descriptor to eight times the actual quantity of licenses served by the license daemon. For example, if your license file has 1,024 licenses, set the soft limit of the socket descriptor to 8192. This change ensures that enough sockets are available. Depending on the TCP/IP setting on your machine, it can take several minutes for the server machine to release the socket resources.

---

## TCP and Network Settings

Do not change any TCP settings on the server machine. If you have made any changes to the default settings, the license server might not operate properly.

Make sure the network card is configured for full duplex communication. In addition, make sure the network switch is configured for 1 GBps data transmission.

---

## WAN License Servers

Synopsys provides the optional capability to host on a WAN (this applies to situations where the distance between the client and server is greater than 5 miles). You must have a contractual agreement with Synopsys to host a license server on your global network. If you need this capability, but are not contracted for it, contact your sales representative.

If you are planning to host a license server on a WAN, make sure that you meet the following requirements:

- A single-server configuration is mandatory if you are setting the license server over a WAN. A redundant license server configuration increases the license checkout delays for the application.
- If the network latency is more than 30 milliseconds between the license server machine and the client machine, you will see performance degradation in the application startup. It is recommended that the license administrator evaluate whether the performance degradation due to network latency is acceptable to end-users before setting up the WAN servers.

Use the `ping` command to see the network latency. The usage in the following example assumes that you are logged on to the client and `elvis` is the server:

```
% ping elvis
PING elvis (10.15.43.201) 56(84) bytes of data.
64 bytes from elvis (10.15.44.206): icmp_seq=0 ttl=253 time=0.706 ms
64 bytes from elvis (10.15.44.206): icmp_seq=1 ttl=253 time=0.267 ms
64 bytes from elvis (10.15.44.206): icmp_seq=2 ttl=253 time=0.293 ms
64 bytes from elvis (10.15.44.206): icmp_seq=3 ttl=253 time=0.241 ms
64 bytes from elvis (10.15.44.206): icmp_seq=4 ttl=253 time=0.455 ms
```

This example shows the usage of the `ping` command on the AMD64 platform (using version 5 of the Red Hat Enterprise Linux operating system). For other operating systems and platforms, please check the man pages for the `ping` command to determine the appropriate usage in order to determine the network latency between the server and the client.

- Some applications check out more than one license, which might cause the tool to take longer to complete the job. Evaluate all the tools in your WAN to find out whether the license checkout delays are acceptable to the end user.
- Make sure that you have no more than two license servers in your license server search path. In addition, evaluate the delay while pointing to multiple license servers.

Set up the WAN servers only after evaluating the these requirements.

---

## Compute Farm and License Server

If you are using a compute farm, make sure that the license server and the compute farm are located within the same subnet. In addition, make sure that the license server meets the hardware and OS requirements as recommended by Synopsys.

---

## Network Mounted File System

Install SCL on a local disk. Also, save the license key file, options file, and report log on the local disk. If these files are saved on a network disk, any glitches to the network file system will adversely impact the license server.

---

## Options File Use Guidelines

You should not invoke the `lmreread` command on a license server to read the changes made to the options file. Instead, restart the license server if you want the changes from the options file to be read properly by the license server.

All option file key words must be specified in uppercase letters, such as `RESERVE`, `INCLUDE`, `EXCLUDE`, and so forth. Keywords specified in lowercase letters are not recognized.

If you have `PACKAGE` lines in the license key file, do not specify any license checkout policies such as `RESERVE`, `INCLUDE`, or `EXCLUDE` in the options file for any package or its components. Packages already have a license checkout policy, and specifying any license checkout policies might conflict with the policy specified in the options file.

The `TIMEOUT` and `TIMEOUTALL` keywords should never be used in the options file because they might conflict with the Synopsys heartbeat mechanism. These keywords tell the license server to release the license keys after a specified period of time. This causes the server to release the license keys if the application is idle.

After a period of time, the application sends a heartbeat message to the license server, and the server will reissue the license keys available from the license pool since there are no license keys checked out for the application. However, if all the license keys are consumed by other applications, the active application instances get license denials. This might result in unpredictable behavior by the application and might even cause the application to abort.

In addition, the license server might behave erratically if the `TIMEOUT/TIMEOUTALL` directive is enabled in the options file.

The `RESERVE` keyword should not be used in the options file especially for `PACKAGEs` licenses if the license has the `SUITE_RESERVED` option. These two options together are not supported. This is because the `RESERVE` keyword in the option file has static information about the key reservation policy. However, when the license keys are checked out by the users, the `SUITE_RESERVED` option within the `PACKAGE` dictates an additional reservation policy which will dynamically change depending on the product usage pattern. They are conflicting requirements if both the options are to be supported together.

---

## Requirements for Starting the SCL Server

To start the `snpslmd` vendor daemon properly, you must unset the following environment variables if they are set:

- `AVANTD_LICENSE_FILE`
- `LM_LICENSE_FILE`
- `NASSD_LICENSE_FILE`
- `SANDWORK_LICENSE_FILE`
- `SNPSLMD_LICENSE_FILE`
- `SYNPLCTYD_LICENSE_FILE`
- `TMALD_LICENSE_FILE`

Unset these variables in the license server startup script. For example, for the Bourne shell, add:

```
% unset AVANTD_LICENSE_FILE  
% unset LM_LICENSE_FILE  
and so on
```

When you start SCL on UNIX or Linux platforms, you should see the following message:

```
23:20:46 (snpslmd) Serving features for the following vendor names:
snpslmd  adalmd  anagram  archprod  avantd  CADABRA  chrysalisd  EPIC
everest  hscd   innologd  ISE-TCADD  la_dmon  leda   metasoftd  nassd
numeritchd  pdld  saber_dmn  sandwork  sigmacd  slat   snpsOEM1  snpsOEM2
snpsOEM3  snpsOEM4  snpsOEM5  snpsOEM6  snpsOEM7  snpsOEM8  snpsOEM9
ssilmd   synopsysd  synplctyd  TE_CATS  tmaId   vcsd
```

If you do not see this message in the daemon log file, the daemon will not be able to serve keys for secondary vendor daemons (avantd, tmaId, nassd, numeritchd, and so forth). Unsetting these variables and restarting the server should resolve this problem.

---

## Legacy Application Compatibility With SCL

Some legacy versions of Synopsys tools are not compatible with the SCL license server. For example, any application built on FLEXlm 4.x or earlier is not compatible with SCL. You can locate the FLEXlm (or FLEXnet) version of an application by using the `lmver` utility that is included with SCL.

For example, to locate the Hercules tool version, enter

```
% lmver /synopsys/hercules/2000.4.4/bin/SUN.64/hercules
```

```
lmver - Copyright (c) 1989-2007 Macrovision Europe Ltd.
and/or Macrovision Corporation. All Rights Reserved.
```

```
FLEXlm v7.0d (liblmgr.a), Copyright (C) 1988-1999
Globetrotter Software, Inc. (https://solvnet.synopsys.com/
EnterACall).
```

From this example, you can see that the 2000.4.4 version of Hercules is based on FLEXlm 7.0d.

The following are known compatibility issues with SCL. If you are using any of the tool versions included in the following list, contact the Synopsys Support Center at

<https://solvnet.synopsys.com/EnterACall>

- HSPICE and AvanWaves version 2000.4 and earlier are not compatible with the `snpslmd` vendor daemon. Contact your Synopsys Account Manager for assistance.

- Proteus, ProGen, and Prospector version 2004.09-7 and all subsequent releases of 2004.09-x have issues related to license queuing with the SCL license server. Contact your Synopsys Account Manager for assistance.
- Synthesis products version 1999.05 and earlier require `synopsysd` authentication in the key file. Contact your Synopsys Account Manager for assistance.
- Former EPIC products version 5.3 and earlier require `EPIC` authentication. Contact your Synopsys Account Manager for assistance.
- Vera version 4.0, 4.1(.x), 4.2, and 4.3 require `ssilm` authentication in the key file. Contact your Synopsys Account Manager for assistance.
- Apollo version 2003.06-SP1 does not work with the `snpslmd` vendor daemon. Contact your Synopsys Account Manager for assistance.
- JupiterIO (formerly PIP) versions W-2005.03 and earlier on the Solaris platform will not work with the `snpslmd` vendor daemon. Contact your Synopsys Account Manager for assistance.

[Table 2-1](#) lists additional software and the associated versions that are not compatible with the SCL license server.

*Table 2-1 Product Versions Incompatible With the SCL Server*

<b>Product</b>	<b>Version incompatible with combined license daemon</b>
Aurora	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
CHIPit	All versions released earlier than 2009.06
Davinci	All versions released earlier than 1999.2 (1999.2 and later work with SCL)
DFM WorkBench	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
Medici	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
Michelangelo	Not compatible
Proteus (Taurus OPC)	All versions released earlier than 2000.4 (2000.4 and later versions work with SCL)
Raphael	All versions released earlier than 1999.4 (1999.4 and later versions work with SCL)

*Table 2-1 Product Versions Incompatible With the SCL Server (Continued)*

<b>Product</b>	<b>Version incompatible with combined license daemon</b>
Raphael NES (RANES)	All versions released earlier than 2002.2 (2002.2 and later versions work with SCL)
Taurus Layout	All versions released earlier than 2002.2 (2002.2 and later versions work with SCL)
Taurus Process / Device [with or without PMEI]	All versions released earlier than 1999.2 (1999.2 & later work with SCL)
Taurus Topography	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
Taurus Visual	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
Taurus WorkBench	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
TSUPREME-3	Not compatible
TSUPREME-4	All versions released earlier than 1999.2 (1999.2 and later versions work with SCL)
Synthesis Tools (Design Compiler, Design Vision, HDL Compiler, DFT Compiler, Design Compiler FPGA, Library Compiler, Physical Compiler, Power Compiler)	All versions released earlier than 1997.08 (3.1, 3.2, 3.3, 3.4, 3.5, 1997.01)

# 3

## Before You Install Synopsys Common Licensing Software

---

This chapter describes tasks you perform before installing and configuring Synopsys Common Licensing (SCL). Before you install the SCL software the first time, you need to complete most of the tasks described in this chapter. Whenever you change your licensing network, you must repeat these tasks. This chapter explains the `sssverify` utility and common licensing network configurations.

Information in this chapter applies to SCL on both UNIX and Windows platforms.

This chapter includes the following sections:

- [Checking the Integrity of the License File](#)
- [License Server Configurations](#)

---

## Checking the Integrity of the License File

When you receive a new Synopsys license key file, it is mandatory that you run the `sssverify` utility (`sssverify` replaces `lmcksum`). The `sssverify` utility validates the integrity of the license file and detects any formatting errors in the file. You must also use this utility whenever the license file is updated.

The following topics are included in this section:

- [Using sssverify](#)
- [Mapping Features to Products](#)

---

### Using sssverify

You must use the complete SCL license file as received from Synopsys. Do not edit or merge the SCL license file with other license files.

#### Important:

Synopsys license files in the combined vendor daemon format include security keys that the `snpslmd` vendor daemon uses to validate the authenticity of your license file and verify that keys have not been added or subtracted. Temporary license keys include the `SSST` feature in the key file. Monthly Technology Subscription Licenses (also known as peak licenses) and other types of revenue keys include the `sss` feature.

Before starting the license server, you should verify the license key file by running the `sssverify` utility by entering the following code:

```
% cd scl_root/platform/bin
% sssverify /path/to/synopsys.lic
```

For additional information about `sssverify`, see [“Using sssverify to Troubleshoot a Synopsys License File”](#) on page 9-10.

---

### Mapping Features to Products

The `sssverify` utility can display all features associated with a product. The information displayed is comprehensive if the license file has an unmodified product comment section as received from Synopsys.

Use the following syntax to run the `sssverify` utility:

```
sssverify license_file [-pinfo | -ptof product_name | -ftop \
  feature_name] [-o <output-file>] [-help]
```

Option	Description
<i>license_file</i>	Your Synopsys license file.
<code>-pinfo</code>	Displays all the product names and the associated features in the license file.
<code>-ptof</code> <i>product_name</i>	Displays all the features associated with a product.
<code>-ftop</code> <i>feature_name</i>	Displays the product and all associated features.
<code>-o</code> <i>output_file</i>	Redirects the product feature information to a file.
<code>-help</code>	Displays help information.

**Note:**

The `-ptof` option will not work if product comment lines have been removed. The `-pinfo` option will work but will not display product names.

---

## License Server Configurations

This section describes the following common configurations for licensing systems:

- [Single Server](#)
- [Multiple Single License Servers](#)
- [Three-Server Redundancy](#)
- [License Server Configurations Summary](#)

For licensing systems that use more than one server, for each server you must take into account the considerations and tasks described in this section.

---

### Single Server

You can configure your license system to use a single server to which all clients refer for their license requests. In this case, you set the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` environment variable on each client node to refer to the single server. (Legacy software versions sometimes require the use of the `LM_LICENSE_FILE` environment variable).

For detailed instructions on setting the license environment variable on UNIX and Windows systems, see [“Describing the License Environment Variables” on page 6-4](#).

**Note:**

It is recommended that you use *port@host* to set the environment variable.

---

## Multiple Single License Servers

You can configure a client to refer to multiple single (distributed) license servers with each server serving a unique subset of all your licenses. In this way, you can distribute all your licenses across multiple servers.

To enable the use of multiple single license servers, you assign a list of servers to the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` license environment variable on the client node. (Legacy software versions sometimes require the use of the `LM_LICENSE_FILE` environment variable.) To specify multiple distributed servers, use a colon (:) as the delimiter. The following example illustrates this specification for a UNIX system:

```
% setenv SNPSLMD_LICENSE_FILE 27000@Server1:26585@server4
% setenv LM_LICENSE_FILE 7182@Server2:1700@Server3
```

Set the `LM_LICENSE_FILE` or `SNPSLMD_LICENSE_FILE` environment variable to *port@host*, by using the port and host values specified on the `SERVER` line in the license key file.

For detailed instructions on setting the license environment variable on UNIX and Windows systems, see [“Describing the License Environment Variables” on page 6-4](#).

## Three-Server Redundancy

Three-server redundancy is a license server configuration in which the same license key file is installed on three separate server nodes so as to provide continued operation in the case of a single node failure.

**Caution:**

Never use redundant servers over a WAN. For a local area network (LAN), use of redundant servers is supported but not recommended. This method is not very robust and can cause the server system to lose communication.

In addition, do not use the `lmreread` utility on large license files or on redundant servers. This utility is unreliable and can put the server in an unpredictable state. Sometimes on large license files, it might take several minutes to reread the license file. During this time, license denials are issued.

With three-server redundancy, the system remains functional and distributes its full complement of licenses as long as any two of the three license servers (a quorum) remain active. If the first master server fails, another is chosen transparently (without your intervention).

At least two of the three servers must be running at all times. On each client, set the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` environment variable to refer to each of the three servers. (Legacy software versions sometime require the use of the `LM_LICENSE_FILE` environment variable.) To specify multiple redundant servers, use a colon (:) as the delimiter.

For detailed instructions on setting the license environment variable on UNIX and Windows systems, see [“Describing the License Environment Variables” on page 6-4](#).

## License Server Configurations Summary

You can use the information provided in [Table 3-1](#) to help you determine the optimal license server setup for your site.

*Table 3-1 License Server Configuration Summary*

Single server	Multiple single server (distributed)	Three-server redundancy
<b>Advantages</b>		
Easy administration and monitoring - Single license file - Single server	Licensing distributed among multiple servers according to use patterns No single point of failure	Fault tolerant - No single point of failure - All licenses are available if two servers are up (quorum)
Simple to understand	Some licenses almost always available	One license file for all licenses
Single point for all licensing activity	Easy to understand	Automatic rollover
<b>Disadvantages</b>		
Single point of failure	Server loss = Some licenses not available	Quorum loss = No licenses
Not scalable	Complex maintenance	Requires a robust network; redundant servers could introduce problems Each server must be maintained in its own environment
<b>Recommended use</b>		

Table 3-1 License Server Configuration Summary (Continued)

Single server	Multiple single server (distributed)	Three-server redundancy
Small to medium sites Sites where a central server controls all data	Geographically dispersed medium to large sites Sites that require fault tolerance	Not recommended

**Note:**

Use the information in [Table 3-1](#) as a general reference only, taking into account special requirements for your site.

## Selecting Host Nodes to Be Used As Servers

Whether you use a single server, distributed servers, or three-server redundancy, you need to identify the nodes to use as the license server host and communicate the host ID information about the server nodes to Synopsys. You can determine the host ID by using the `lmhostid` command.

**Important:**


Depending on your hardware and system configuration, you might see degradation in response times when the server goes above 1,000 simultaneous connections. In this case, it is recommended that you divide features among license servers.

## Standard FLEXnet License File List Behavior

Standard FLEXnet license file list behavior is implemented in all Synopsys tools. For standard license file list behavior, servers are queried in the order listed in the license file list as specified in the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` environment variable settings. If the requested license is not available on the first server, the next one is tried, and so on.

[Figure 3-1](#) illustrates standard FLEXnet server selection behavior. For this example, assume that these four servers are listed in the following order in the license file list: Server1, Server2, Server3, and Server4. If Server1 can satisfy the license request, that server is used for all subsequent requests. If it cannot, then the next server specified in the license file list, Server2, is tried, and so on, until one of the servers specified in the list satisfies the license. [Figure 3-1](#) shows this scenario.

Figure 3-1 Standard FLEXnet License File List Server Selection Behavior



### Rollover Behavior When Server Goes Offline

Following standard FLEXnet behavior, if the Synopsys tool loses its connection to the currently used server, it attempts to locate a replacement server. The tool locates and connects to the first server identified in the license file list (specified by `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE`) that offers the required license.

The client application is terminated only if no other server specified in the license file list can satisfy the license requirement. For additional information about rollover behavior, see [“Rollover Functionality” on page 2-2](#).



# 4

## Downloading SCL Software and Obtaining License Key Files

---

This chapter includes these sections:

- [Registering for SolvNet and Downloading SCL](#)
- [Obtaining the Synopsys License Key File](#)

---

## Registering for SolvNet and Downloading SCL

To download Synopsys Common Licensing (or any Synopsys software) by Electronic Software Transfer, or to obtain license keys from SmartKeys, you must be registered for SolvNet.

To register for SolvNet, go to the SolvNet Web page at <https://solvnet.synopsys.com> and click Register Today. (This site also has information on how to retrieve a lost user name or password.)

Note:

To register for SolvNet you must have a corporate e-mail address and know your Synopsys site ID. If you do not know your site ID, obtain it from your site administrator or from your sales representative.

To download SCL software, obtain the download instructions for SCL 11.1 from the Download Center at <https://solvnet.synopsys.com/DownloadCenter>.

Complete instructions for installing SCL are available in the Synopsys Common Licensing chapter of the *Synopsys Installation Guide* at

<http://www.synopsys.com/Support/Licensing/Installation/Pages/default.aspx>

---

## Obtaining the Synopsys License Key File

This section describes how to obtain a soft copy of your license key file from Synopsys by using the SmartKeys delivery system. It includes the following sections:

- [About the License Key File](#)
- [Logging In to SmartKeys](#)
- [Retrieving Term Licenses](#)
- [Retrieving Monthly Technology Subscription Licenses](#)

---

### About the License Key File

Licensing data required for SCL to grant licenses is stored in a text file called the license key file. Synopsys creates the license key file containing all the information required to grant (or deny) license requests based on your purchased products and license availability.

When a new order is placed, Synopsys sends the license key file by e-mail to the registered site contact. Alternatively, anyone who is registered in SolvNet for a given site can retrieve the keys.

See [Chapter 7, “Explaining the License Key File”](#) for an example license key file and details about how to interpret the license key file contents.

---

## Logging In to SmartKeys

You can access SmartKeys through SolvNet (click Documentation & Downloads Center, then click SmartKeys) or directly from the SmartKeys Web page at

<https://solvnet.synopsys.com/SmartKeys>

If requested, enter your SolvNet user name and password.

### Note:

You can retrieve keys for registered sites only. To determine the sites you are registered for or to add a site, log on to SolvNet at <https://solvnet.synopsys.com> and click [My Profile](#) at the top of the page.

On the SmartKeys Web page, click Key Retrieval to retrieve your latest technology subscription licenses, or click “Monthly TSL Redemption” to generate and retrieve any available monthly technology subscription licenses.

Technology subscription licenses are long-term keys that are regular licenses defined by an explicit contract period, typically one, three, or five years. Typically, these keys are issued for one year at a time. When the keys expire, they are extended for another year until the contract period expires.

Monthly technology subscription licenses (peak keys) are short-term licenses that are prepurchased to handle peak usage situations. Typically, these licenses can be redeemed for any 30-day range within the redemption period, which is usually a year. A monthly technology subscription license expires at the end of the redemption period—even if it has not been redeemed.

---

## Retrieving Term Licenses

From the SmartKeys Web site,

1. Click Key Retrieval.
2. Enter the following information in the fields of the Key Retrieval dialog box:
  - Site ID (required)

This is the Synopsys site ID number of the site for which you want to obtain term license keys. You can retrieve keys only for sites for which you are registered. Also, you can retrieve keys only for one site ID at a time. (For additional sites, make a new request.)

- Attachment option – The default value is ASCII text format.

Do not change this option unless you are unable to receive text file (.txt) attachments by e-mail.

3. Click Continue to submit your request. The license key files for the chosen site are e-mailed to your SolvNet-registered e-mail address.

---

## Retrieving Monthly Technology Subscription Licenses

From the SmartKeys Web site,

1. Click Monthly TSL Key Redemption.
2. Enter the correct site ID in the Site ID dialog box, then click Continue.
3. On the License Redemption Selection page, check the box next to the desired “Sales doc” number, then click Continue.

Note:

This line also contains other descriptive information to assist you in making the right choice. For example, information about the Synopsys material number, material description, remaining quantity, and redemption period are included.

4. On the Monthly TSL Key Redemption License Details page, enter the necessary information in the appropriate text box:
  - Withdrawal QTY – Enter the number of keys desired, up to the quantity available.
  - Start Date – Enter the desired start date.
  - Host ID 1 – Enter the host ID for the license server. The host ID must match the results of the `lmhostid` command (the `lmhostid` utility is included with SCL), and the license server must be running a supported hardware platform and operating system. For detailed platform information, go to <http://www.synopsys.com/Support/Licensing/SupportPlatform/ReleaseSupport/Pages/default.aspx>
  - Host ID 2 (Optional) – For redundant servers only (not recommended). Enter the host ID for the second license server (of three).
  - Host ID 3 (Optional) – For redundant servers only (not recommended). Enter the host ID for the third license server (of three).

**Note:**

It is strongly recommended that your monthly technology subscription license keys be hosted on a different license server than your production (long term) licenses. This ensures that the production server is not impacted.

5. Click Next to continue.
6. Click Generate to have the keys sent to the registered SolvNet e-mail address.



# 5

## Configuring and Verifying the License Key File

---

This chapter provides detailed information on configuring and verifying the license key file on UNIX and Windows systems. The following sections are included:

- [Viewing the SCL Licensing Installation Directory Structure](#)
- [Verifying the License Key File](#)
- [Required License Key File Modifications](#)
- [Locating and Using the Options File](#)

Note:

For detailed information about using SCL on Windows platforms, see [Appendix A, "Starting SCL on Windows Platforms With LMTTOOLS."](#)

## Viewing the SCL Licensing Installation Directory Structure

The installation program installs the software into a directory structure created by the SCL installation program as shown in [Figure 5-1](#). This directory structure is the same for all platforms. Only the platform directory name will change, depending on the platform you are installing. For example, *platform* might be amd64 for AMD64 or windows for Windows.

Figure 5-1 Installation Directory Structure and File Location and Description




Table 5-1 describes the directories created by the installation program and the installed files.

Table 5-1 Installation Directory Structure and File Location and Description

Root and top-level directories	Subdirectories and files
scl_root	This is the root directory for the SCL software created by the installation program. This directory contains the following subdirectories: examples, admin, docs, <i>platform</i> .
examples	This directory includes setup files and example scripts that you can modify for your site, including a UNIX startup script (which must be modified with site-specific information).
admin	The admin directory contains the following subdirectories: license and logs.  /license – This directory is provided as a possible location for the license key file. You can store the license key file where most convenient for your site. There is no default or required location for it.  /logs – The installation process creates this empty directory to which you can later install log files resulting from <code>snpslmd</code> daemon processing.
docs	This directory contains the SCL documentation. It includes the following files: <ul style="list-style-type: none"> <li>• FLEXNetLicensingEndUserGuide.pdf - This document contains information required by FLEXnet Licensing to manage licenses for a FLEXenabled application</li> <li>• FLEXnet_ID_Dongle_Drivers.pdf - This document contains information about FLEXNet Dongle Drivers</li> <li>• SCL_11.1_Administration_Guide.pdf - This file delivers the <i>Synopsys Common Licensing Administration Guide</i></li> <li>• SCL_11.1_install.pdf - This file delivers the <i>Synopsys Common Licensing Installation Guide</i></li> <li>• SCL_11.1_Release_Notes.pdf - This document contains release notes that give brief installation and setup information as well as late-breaking news about SCL</li> </ul>
drivers	The directory described in contains the various dongle drivers required to use a dongle as a license server.

*Table 5-1 Installation Directory Structure and File Location and Description (Continued)*

Root and top-level directories	Subdirectories and files
platform	<p>This directory contains the following subdirectories</p> <p>/bin – For each supported platform architecture (after which the directory is named), the bin subdirectory contains the same set of executable files. This directory contains the following SCL executable files, including the SCL daemons and utilities:</p> <ul style="list-style-type: none"> <li>• <code>lmgrd</code> – This executable file is the standard FLEXnet license server daemon.</li> <li>• <code>snpslmd</code> – This executable file is the SCL vendor daemon.</li> <li>• <code>lmutil</code></li> <li>• <code>lmver</code></li> <li>• <code>lmstat</code></li> <li>• <code>lmreread</code></li> <li>• <code>lmremove</code></li> <li>• <code>lmhostid</code></li> <li>• <code>lmdown</code></li> <li>• <code>lmdiag</code> – These executable files are standard FLEXnet utilities delivered with SCL.</li> <li>• <code>sclsh</code> – This executable file is the SCL shell, which you can run to test the licensing daemon.</li> <li>• <code>whatscl</code> – This executable file returns the version of SCL that you are running.</li> <li>• <code>sssverify</code> – This executable file verifies the integrity of your license file.</li> </ul>

You should use the Synopsys Installer to install the SCL software. For SCL configuration and start-up instructions, see [Chapter 6, “Starting the SCL Server on UNIX and Windows Systems.”](#)

To download SCL via Electronic Software Transfer, download the `scl_v11.1_common.tar` file as well as the platform specific tar file you need. For example, for AMD64 you should download the `scl_v11.1_amd64.tar` or the `scl_v11.1_linux.tar` file.

The Synopsys Installer defaults to the following root directory: `/usr/synopsys/SCL_11.1`

Additional directories are under this directory, such as:

`/usr/synopsys/SCL_11.1/amd64/bin/snpslmd`

For the Windows platform, the default install directory is `C:\synopsys\SCL_11.1`

After installation, the directory looks like this:

```
C:\synopsys\SCL_11.1\windows\bin\snpslmd.exe
```

Synopsys also provides various dongle drivers for Windows and Linux platforms, which are required to use a dongle as a license server on Windows.

Drivers for the Windows platforms are included under this directory:

```
C:\Synopsys\SCL_11.1\windows\drivers
```

Drivers for the linux platform are included under this directory:

```
/usr/synopsys/SCL_11.1/linux/drivers
```

---

## Verifying the License Key File

This section describes how to determine if your license key file includes the correct host ID and how to verify that the license key file is valid.

The following sections are included:

- [Verifying the License Key File Host ID](#)
- [Checking the License Key File for Errors](#)
- [Avoiding License Key File Errors](#)
- [Placing the License Key File on Your System](#)

---

## Verifying the License Key File Host ID

Use the `lmhostid` utility included with SCL to verify the license server host ID. For example,

### UNIX – AMD64 (amd64)

In the following example, the host ID of the machine is 83a54cb9.

```
/synopsys/scl/11.1/amd64/bin> lmhostid
```

```
lmhostid - Copyright (c) 1989-2008 Acrecco Software Inc. All Rights Reserved.
```

```
The FLEXnet host ID of this machine is "83a54cb9"
```

### Windows

In the following example, the host ID of the machine is 000f1f2fae0b:

```
C:\synopsys\SCL_11.1\windows\bin> lmhostid
```

```
lmhostid - Copyright (c) 1989-2008 Acresto Software Inc. All Rights Reserved.
```

```
The FLEXnet host ID of this machine is "000f1f2fae0b"
```

If the host ID number of your license server does not match the host ID specified on the SERVER line, locate the correct server or if there is no such server, contact your local sales representative.

---

## Checking the License Key File for Errors

You must use the `sssverify` utility to check the license key file for errors before you install it. Errors in the license key file can result in license acquisition failures or denials. For detailed information about `sssverify`, see [“Checking the Integrity of the License File” on page 3-2](#).

Before running `sssverify`, check the license key file for errors. At a minimum, check the following lines:

**SERVER line:** Make sure the SERVER line specifies the correct host name for the host ID. The host name is the first parameter; the host ID is the second parameter. Errors on the SERVER line can cause startup failures.

Be sure to change the specified TCP port (27000) if your site is using another TCP port for SCL (`lmgrd`). For details on the SERVER line, see [“The SERVER Line” on page 7-3](#).

**VENDOR line:** Make sure the VENDOR line correctly specifies the SCL `snpslmd` daemon, followed by the full path to the `snpslmd` daemon. Errors on the VENDOR line can cause startup failures.

If you modified this line to include a path to the options file for the DAEMON line, ensure that the daemon is correct. For details about VENDOR line requirements, see [“The VENDOR Line” on page 7-4](#) of this guide.

---

## Avoiding License Key File Errors

The following rules are mandatory. To avoid errors in the license key file, it is necessary that you follow these guidelines:

- Always run `sssverify` after modifying the license file.
- Always treat the license file as a unit:

- Never modify your license file by adding or removing licenses from another file, including keys from old Synopsys licenses or another vendor. (The only exception to this rule is temporary keys, which can be appended to your production key file if they are not invalidated by production keys with a later `ISSUED` date.)
- Other than modifiable fields (the `VENDOR` or `DAEMON` path and the `SERVER` name or port number), do not add any information to the license key file.
- Do not combine expired keys with the new key file. Combining older production keys with newer production keys will invalidate the license key file and result in checkout errors or denials.
- Always use the latest versions of FLEXnet daemons and utilities packaged with SCL. Never use `lmgrd` from another vendor or if from an earlier release of a Synopsys tool. Using older versions from other vendors or old Synopsys installs can cause licensing failures.
- SCL and all components (the license key file, options file, and debug log file) must be locally mounted.

---

## Placing the License Key File on Your System

You can install the license key file in any locally mounted directory. However, when you install the SCL software, the installation program creates a directory called `scl_root/admin/license`. This is the recommended location for the license key file.

The license key file identifies the server to be used by the application. For Synopsys tools to find the license server, you must specify its location by using one of the environment variables. See [“Describing the License Environment Variables” on page 6-4](#).

---

## Required License Key File Modifications

The license key file is an ASCII text file that contains licensing data required for SCL to serve licenses. You can use the license key file after modifying the host name value on the `SERVER` line and the path information on the `VENDOR` line.

For a detailed explanation of the license key file, see [Chapter 7, “Explaining the License Key File”](#) or the *FLEXnet Licensing End Users Guide*.

### Caution:

Do not change any data items in the license key file other than those identified in this section as modifiable. Host ID information, as well as `INCREMENT` and `PACKAGE` lines, are encrypted. If you change these items, you will invalidate the license keys.

The following topics are included in this section:

- [Modifying SERVER Line Data Items](#)
- [Modifying VENDOR Line Data Items](#)

---

## Modifying SERVER Line Data Items

You can modify the following data items on the SERVER line; otherwise, default values are assumed:

- The *host name*

You must change the default host name *hostname1* supplied as a placeholder by Synopsys, replacing it with the actual host name for your server node.

Note:

For redundant servers, the license key file has three SERVER lines specifying *hostname1*, *hostname2*, and *hostname3*.

The host name argument is a string returned by the UNIX `host name` or `uname -n` command, or an IP address in the `###.###.###.###` format. When you edit this field, use the IP address if the server node has multiple network interfaces (and therefore, multiple host names), or for sites where the Network Information Service (NIS) or domain name structure (DNS) has trouble resolving a host name.

- The *port-number*

The license key file you receive from Synopsys specifies a default TCP port number of 27000. To use an explicit port number other than the default, specify a number within the range of 1024 through 64000 inclusive.

After you install and run the licensing software, if you modify the server host name or the TCP port number of the server, you must shut down the licensing system by using `lmdown` and restart the `lmgrd` daemon for these changes to be enacted. (The `lmreread` utility will not cause these specific changes to take effect.)

---

## Modifying VENDOR Line Data Items

Synopsys tools require an active license server daemon at all times. SCL includes the standard `lmgrd` FLEXnet license server daemon and the `snpslmd` Synopsys vendor daemon.

The `snpslmd` daemon supports all synopsys vendor daemons. Therefore, only one vendor daemon is needed for all Synopsys tools.

A license server machine can have only one active `snpslmd` daemon at a time. No other Synopsys vendor daemons can run on the server with `snpslmd`.

For distributed license networks, you must start the `lmgrd` daemon on each license server. For instructions on starting the license server daemon, see [“Starting the SCL License Server Daemon” on page 6-2](#).

The `VENDOR` line, specifies the `snpslmd` Synopsys daemon name and path and a daemon options file. The `VENDOR` line also allows you to specify a port number to be used if you make connections through an Internet firewall. Many Internet firewalls require that port numbers to the firewall be specified.

The `lmgrd` license server daemon uses the `VENDOR` line to locate and start the Synopsys `snpslmd` daemon. The Synopsys `snpslmd` daemon refers to this line for path information to its options file. (You can provide an options file to specify various operating parameters of the license server such as access control.)

## Syntax

```
{VENDOR} daemon_name [daemon_path] \
      [options=options_path] [port=] port_number
```

Here is the `VENDOR` line as it exists unmodified in the license key file:

```
VENDOR snpslmd /path/to/snpslmd
```

### Important:

You must specify the full path for the `snpslmd` vendor daemon on the `VENDOR` line.

Here is the same `VENDOR` line modified to give the path to the location where the `snpslmd` daemon is stored, as well as an options file location with a fully qualified path:

```
VENDOR snpslmd scl_root/amd64/bin/snpslmd \
options=scl_root/amd64/admin/snpslmd.opt
```

If you provide an options file and choose to accept the default location rather than explicitly specify the file's location, you must name the file `snpslmd.opt` and store it in the same directory as the license key file. (See [“Locating and Using the Options File” on page 5-10](#) for information on how to create the file.)

If you specify an options file, it is recommended that you use the `options=` keyword in conjunction with the options file path.

You can check the debug log file to verify that the license key file and options file were found and properly read. (You must have write access to the directory containing the `debug.log` file.)

For details about the debug log file, see [“Using the Debug Log File to Troubleshoot License Issues” on page 9-17](#).

---

## Locating and Using the Options File

Use of an options file enables a finer degree of access control over licensed features. You can use the file to allow or restrict access to licensed features for certain users or machines, based on user names, host names, display names, or IP addresses. You can also reserve licensed features using these same categories.

The `snpslmd` daemon looks at the `options=path` value on the `VENDOR` line in the license key file for a specified path. If you do not specify the path, the file must be named `snpslmd.opt` and must reside in the same directory as the license key file.

You should not invoke the `lmreread` command on a license server to read the changes made to the options file. Instead, restart the license server if you want the changes from the options file to be properly read by the license server.

All option file key words must be specified in uppercase letters, for example, `RESERVE`, `INCLUDE`, `EXCLUDE`, and so on. Keywords specified in lowercase letters are not recognized.

If you have `PACKAGE` lines in the license key file, do not specify any license checkout policies such as `RESERVE`, `INCLUDE`, or `EXCLUDE`, in the options file for any package (or its components). Packages already have a license checkout policy, and this might conflict with the policy specified in the options file.

The `TIMEOUT` and `TIMEOUTALL` keywords should never be used in the options file because they might conflict with the Synopsys heartbeat mechanism. These keywords tell the license server to release the license keys after a specified period of time. This causes the server to release the license keys if the application is idle.

After a period of time, the application sends a heartbeat message to the license server, and the server will reissue the license keys available from the license pool since there are no license keys checked out for the application. However, if all the license keys are consumed by other applications, the active application instances get license denials. This might result in unpredictable behavior by the application and might even cause the application to abort.

In addition, the license server might behave erratically if the `TIMEOUT/TIMEOUTALL` directive is enabled in the options file.

The `RESERVE` keyword should not be used in the options file on a `PACKAGE` license if the license has the `SUITE_RESERVED` option. These two options together are not supported. This is because the `RESERVE` keyword in the option file has static information about the key

reservation policy. However, when the license keys are checked out by users, the SUITE\_RESERVED option within the PACKAGE dictates an additional reservation policy that will dynamically change depending on the product usage pattern. They are conflicting requirements if both the options are to be supported together.



# 6

## Starting the SCL Server on UNIX and Windows Systems

---

This chapter provides steps for starting the SCL server and information about the license environment variables.

The following sections are included:

- [Starting the SCL License Server Daemon](#)
- [Specifying a Debug Log File](#)
- [Describing the License Environment Variables](#)

---

## Starting the SCL License Server Daemon

Synopsys tools require an active license server daemon at all times. SCL includes two daemons, the standard FLEXnet `lmgrd` license server daemon and the `snpslmd` Synopsys vendor daemon.

The `snpslmd` daemon supports all Synopsys vendor daemons incorporated into SCL. Therefore, only one vendor daemon is needed for all Synopsys tools. (For a list of vendor daemons incorporated into SCL, see [“Synopsys Legacy Vendor Daemons” on page 1-5](#).)

A license server machine can have only one active `snpslmd` daemon at a time. No other Synopsys vendor daemons (including legacy daemons) can run on the server with `snpslmd`.

---

## Starting the License Server on One or More Servers

This section describes how to start the SCL server from the command line and discusses the debug log file.

### Using the `lmgrd` Command to Start SCL

You start SCL on a server by using the `lmgrd` command. This command automatically starts SCL by reading the license key file and starting the `snpslmd` vendor daemon.

For three-server redundancy, you must start the `lmgrd` daemon on each of the three servers listed in the `SERVER` lines of your license key file.

To start SCL 11.1, follow these steps:

1. Modify the license key file. (See [“Required License Key File Modifications” on page 5-7](#).)
2. Stop `snpslmd` and any legacy vendor daemons by using the `lmdown` utility included with SCL. For the Windows OS, you can use `lmtools` to stop the server.

```
% lmdown -c /path/to/synopsys.lic
```

For UNIX platforms, `lmdown` is installed in the `scl_root/platform/bin` directory. For Windows systems, it is installed in the `scl_root\windows\bin` directory. (For optional switches, see the *FLEXnet Licensing End Users Guide*.)

3. Start the SCL 11.1 license server.

Note:

For Windows users, it is recommended that you use `lmtools` to start SCL. For detailed instructions, see [“Starting SCL Automatically With LMTTOOLS” on page A-2](#).

The following example (which starts `lmgrd` and specifies a debug log file) assumes the license key file is stored in the `scl_root/admin/license` directory:

```
% scl_root/platform/bin/lmgrd \
-c scl_root/admin/license/snpslmd.lic \
-l scl_root/admin/logs/debug.log -reuseaddr
```

Replace *platform* with the keyword for your operating system. For a list of SCL keywords, see [Table 1-1 on page 1-3](#).

**Note:**

The `lmgrd` daemon locates and starts the Synopsys `snpslmd` daemon based on path information specified on the `VENDOR` line of the license key file.

4. Check the debug log file to make sure that the server has been started correctly.

The debug log file contains output from the `lmgrd` and `snpslmd` daemons. For details and a sample log file report, see [“Specifying a Debug Log File” on page 6-3](#).

5. (Optional) Use `lmstat` to verify that users are able to check out licenses and to ensure that the license daemon started properly. Output from `lmstat` should show the FLEXnet version and the name of the host used as the license server, followed by the word `UP`.

The following lines indicates that the `snpslmd` daemon is active.

```
Vendor daemon status (on host1):
snpslmd: UP 11.6
```

**Note:**

The `lmstat` utility shows only the major FLEXnet version, for example, 11.6. The minor version (11.6.x.x) is not displayed

---

## Specifying a Debug Log File

When you start the `lmgrd` daemon, you can specify a debug log file to which diagnostic information is directed. (The debug log file receives the output from the `lmgrd` daemon and the `snpslmd` daemon.) For example,

```
lmgrd -c synopsys.lic -l synopsys.log
```

In the previous example, the name of the debug log file is `synopsys.log`. You can specify any name for the log file, for example, `license.log`. Note that you must have write access to the directory containing the debug log file.

[Example 6-1](#) shows an example of debug log file output.

### Example 6-1 Debug Log File Output

```
20:42:05 (lmgrd) FLEXnet Licensing ((v11.6.1.0 build 66138 i86_re3)
started on host1 (linux) (10/16/2009)
20:42:05 (lmgrd) Copyright (c) 1988-2008 Acresto Software Inc. All Rights
Reserved.
20:42:05 (lmgrd) US Patents 5,390,297 and 5,671,412.
```

```

20:42:05 (lmgrd) World Wide Web: http://www.acresso.com
20:42:05 (lmgrd) License file(s): /synopsys/scl/admin/license/
synopsys.lic
20:42:05 (lmgrd) lmgrd tcp-port 27000
20:42:05 (lmgrd) Starting vendor daemons ...
20:42:05 (lmgrd) Started snpslmd (internet tcp_port 39844 pid 2795)
20:42:06 (snpslmd) FLEXnet Licensing version v11.6.1.0 build 66138
i86_re3
20:42:06 (snpslmd) Synopsys Corporate Licensing (SCL) Release: version
SCL_11.1
20:42:07 (snpslmd) Server started on host1 for:SSS
20:42:07 (snpslmd) DC-Expert DC-Ultra-Features DC-Ultra-Opt
20:42:07 (snpslmd) Design-Compiler DesignWare HDL-Compiler
20:42:07 (snpslmd) ISE-TCADD_feat1 all_feat
20:42:07 (snpslmd)
20:42:07 (snpslmd) Licenses are case sensitive for TE_CATS
20:42:07 (snpslmd)
20:42:07 (snpslmd) EXTERNAL FILTERS are OFF
20:42:07 (lmgrd) snpslmd using TCP-port 58416
20:42:07 (snpslmd) Serving features for the following vendor names:
snpslmd adalmd anagram archprod avantd CADABRA chrysalisd EPIC
everest hscd innologd ISE-TCADD la_dmon leda metasoftd nassd
numeritchd pdld saber_dmn sandwork sigmacd slat snpsOEM1 snpsOEM2
snpsOEM3 snpsOEM4 snpsOEM5 snpsOEM6 snpsOEM7 snpsOEM8 snpsOEM9
ssilmd synopsysd synplctyd TE_CATS tmalld vcsd
-----
20:42:09 (snpslmd) Checking the integrity of the license file....
20:42:09 (snpslmd) Valid SSS feature found.
20:42:09 (snpslmd) The feature is needed to enable the other keys in your
license file.
20:42:09 (snpslmd) Licensed to exclusive use of buyer
20:42:09 (snpslmd) Siteid: 1234, Server Hostid: 83915b15, Issued on: 9/
30/2009
-----
20:42:10 (snpslmd) TCP_NODELAY NOT enabled
20:42:13 (snpslmd) OUT: "Design-Compiler" user@hostname2
20:42:13 (snpslmd) OUT: "Design-Expert" user@hostname2
20:42:13 (snpslmd) OUT: "HDL-Compiler" user@hostname2
20:42:14 (snpslmd) IN: "Design-Compiler" user@hostname2

```

---

## Describing the License Environment Variables

This section describes the environment variables that you set on every client to identify the location of the SCL license server to be used. It also describes how to set the environment variables by using *port@host* syntax.

SCL supports use of the FLEXnet vendor-specific license environment variable implemented as `SNPSLMD_LICENSE_FILE` and the standard FLEXnet `LM_LICENSE_FILE` variable.

**Note:**

For additional information about using environment variables on Windows platforms, see [Appendix A, “Starting SCL on Windows Platforms With LMTTOOLS.”](#)

---

## About Environment Variables

To locate the SCL license server to be used, each client must have one of its license environment variables set to point to the software. The license environment variables refer to one or more license servers (or, in the outdated mode, license key files) to be used.

SCL uses the following two license environment variables, common to all Synopsys tools:

- `SNPSLMD_LICENSE_FILE`

This is the Synopsys-specific (vendor) license environment variable. It is recommended that you use the `SNPSLMD_LICENSE_FILE` environment variable because the latest Synopsys tools read this environment variable first. License requests can be handled faster if the Synopsys tools do not have to contact servers from other vendors.

You can assign multiple values to the `SNPSLMD_LICENSE_FILE` variable, but all of these values should refer to SCL license servers, not to other vendor products. If you set this variable to multiple values, the license key files on the servers listed are searched from left to right.

- `LM_LICENSE_FILE`

The `LM_LICENSE_FILE` license variable, which is the FLEXnet default, can be used to refer to multiple license key files, including those provided by vendors other than Synopsys. If multiple file locations are assigned to this variable, the Synopsys tools search those files from left to right to find the requested license.

**Important:**

To speed tool startup, some Synopsys tools do not look at `LM_LICENSE_FILE` if `SNPSLMD_LICENSE_FILE` is set.

---

## Specifying Values for License Software Environment Variables

Although there are several methods you can use to identify the license server to be used, it is recommended that you use the *port@host* method:

- *port@host* – This is the recommended method and should be used for all SCL clients.
- Explicit path or directory – The directory containing the license key file or files with the `.lic` extension. Though still supported, this method is outdated.

[Table 6-1](#) compares the various methods of specifying license key environment variable values.

*Table 6-1 Overview of Methods of Specifying Environment Variable Value*

Notation	Advantages	Disadvantages
<i>port@host</i>	Recommended method. Uses the port number and host name specified on the <code>SERVER</code> line of the license key file. Makes available to the client any updates to the license key file.	A TCP port number for the license server must be explicitly specified in the license key file. You can use the Synopsys default TCP port number of 27000 or choose a number from within the range of 1024 - 64000 inclusive.
explicit path or directory	Use is discouraged. The <code>port@host</code> method is recommended. Continued support provided for historical reasons. This was once the only available method.  Important: Do not remove the <code>USE_SERVER</code> keyword from the license key file. This keyword is required to point to the server when using explicit path syntax.	The file must be mounted, which can cause latency problems and checkout failures.

## Using `port@host` Notation

This is the recommended method of specifying the license server to be used. In this case, you use the port and host values specified on the `SERVER` line in the license key file.

For example,

```
% setenv SNPSLMD_LICENSE_FILE 27000@host1
```

specifies a server with the host name of `host1` and a TCP port of 27000.

---

## Using Environment Variables to Configure Clients for Multiple-Server Access

To configure a client for access to multiple distributed license servers, you set the environment variable to a license file list. All Synopsis tools have the default license file list behavior.

You can configure a client to refer to multiple servers for its license requests. To do so, you assign a list of servers to the license environment variable on the client server. The servers are queried in the order you specify them. If the requested license is not available on the first server, the next one is tried, and so on.

After a client is served a license from a particular server, it must obtain any additional licenses it requests from that server for the duration of the process unless the client can use license server pooling.

To configure a client to refer to its license servers, set the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` environment variable to refer to the list of servers to be queried for the license. The following example uses the `port@host` specification to identify the single server to be queried for licenses for Client1:

```
% setenv SNPSLMD_LICENSE_FILE 27000@Server1
```

If the client has more than one license server, use the license file list format, which has a colon as the delimiter, to set the `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` environment variable to refer to the list of servers to be queried for the license. The following example uses the `port@host` specifications to identify the three servers to be queried for licenses for Client2:

```
% setenv SNPSLMD_LICENSE_FILE 27000@Server1:26585@Server2:28000@Server3
```

Note:

For Windows operating systems, use a semicolon (;) rather than a colon (:) as the delimiter.

## Using Environment Variables to Configure Clients for Three-Server Redundancy

If your license network uses three-server redundancy, (described in [“Using Environment Variables to Configure Clients for Multiple-Server Access”](#) on page 6-7), you can use any of the methods previously discussed to refer to the server to be used. Server redundancy takes effect automatically. If the master server fails, another is chosen transparently without you modifying the configuration.

**Caution:**

A redundant server configuration can be combined with a remote server configuration, although doing so is not recommended. To use a redundant server configuration with a remote server configuration, you can specify the `SNPSLMD_LICENSE_FILE` as follows:

```
setenv SNPSLMD_LICENSE_FILE  
27000@Server1,26585@Server2,28000@Server3:27000@remote_server1:28000@remote_server2
```

Use of redundant servers is not recommended. This method is not very robust and can cause the server system to fail if communication is lost between the servers.

In addition, do not use the `lmreread` utility on large license files or on redundant servers. This utility is unreliable in these situations and can put the server in an unpredictable state.

## Using the `lmdown` Command to Stop SCL

You stop SCL on a server by using the `lmdown` command. This command shuts down the `lmgrd` license server daemon and the `snpslmd` vendor daemon. For three-server redundancy, you must stop the `lmgrd` license server vendor daemon on each of the three servers listed in the `SERVER` lines of your license key file.

To stop SCL 11.1, stop the `snpslmd` vendor daemon and any legacy vendor daemons by running the `lmdown` utility that is included with SCL using the following format:

```
% lmdown -c /path/to/synopsys.lic
```

For UNIX platforms, the `lmdown` utility is installed in the `scl_root/platform/bin` directory. For

Windows systems, it is installed in the `scl_root\windows\bin` directory. Alternatively, for the Windows operating system, you can use `lmtools` to stop the server.

When you have successfully stopped SCL, the debug log file indicates that the daemon has been shutdown.

# 7

## Explaining the License Key File

---

This chapter gives an overview of the Synopsys Common Licensing (SCL) license key file. It includes an example file in the format in which you receive it from Synopsys and provides a description of its contents.

This chapter includes the following sections:

- [About the License Key File](#)
- [The License Key File Header](#)
- [The License Key File INCREMENT Line](#)
- [On-Support Keys](#)
- [SUPERSEDE Keys](#)
- [Synopsys Example License File](#)

---

## About the License Key File

Licensing data required for SCL to grant (or deny) licenses is stored in a text file called the license key file. Synopsys generates the license key file based on the licenses purchased for tools served by a host or all hosts at the specified site.

To obtain the latest key file for your site, log in to SmartKeys a

<https://solvnet.synopsys.com/SmartKeys>

For details on retrieving the license key file through Smartkeys see “[Logging In to SmartKeys](#)” on page 4-3.

SCL allows you to use your license key file with minimal modification. You need only modify the SERVER line (to replace `hostname1` with the name of the license server) and the VENDOR line (to replace `/path/to/snpslmd` with the correct path to the `snpslmd` vendor daemon).

The license key file is designed to use default values for all user-modifiable data items. You can accept default values for the `lmgrd` TCP port (27000) and the `snpslmd` TCP port (determined randomly if not specified).

In addition, the license key file for SCL

- Uses the INCREMENT line rather than the FEATURE line to specify information
- Is case-sensitive
- Reports error messages that are clear and easy to understand

---

## The License Key File Header

[Example 7-3 on page 7-9](#) shows a license key file in the format in which you would receive it from Synopsys. The example file includes a monthly technology subscription license, as well as term licenses. Technology subscription licenses are regular licenses whose duration—defined by an explicit expiration date—is variable, but commonly extends for a year. Monthly technology subscription licenses have a usage limit of 30 days.

This section includes the following topics:

- [License Key File Comment Lines](#)
- [The SERVER Line](#)
- [The VENDOR Line](#)

- [The USE\\_SERVER Line](#)

---

## License Key File Comment Lines

The license key file content is summarized in comment lines at the top of the file so you can see at a glance the kind and number of licenses issued. (The comment lines start with a pound sign (#) and can be removed if desired.)

The following information is provided in the license file comments:

### Product

The material and serial numbers identifying the product, followed by the name of the product for which the licenses are issued. The first number is the material number and is followed by the serial number. Each product has its own material number. Also, a product for which a license was issued in May will have a serial number different from the same product for which a license was issued in January.

### Qty

The number of licenses issued for the particular product.

### Sup\_start

The beginning date of the duration of support purchased for the product.

### Sup\_end

The end date of the duration of support purchased for the product.

### Lic\_Type

The type of licenses purchased. [Example 7-3 on page 7-9](#) shows two of the possible types of licenses: time based and perpetual.

### Lic\_Mode

The mode for which the license was issued. In [Example 7-3 on page 7-9](#), all licenses are networked licenses.

---

## The SERVER Line

The first uncommented line in a license key file is the SERVER line. This line identifies the host node to be used as the server.

Here is the SERVER line from the license key file shown in [Example 7-3 on page 7-9](#):

```
SERVER hostname2 829ED4A0 27000
```

The SERVER line specifies the following fields:

`SERVER` (keyword)

*hostname* (user modifiable)

This is the name of the host machine used as the server. The host name, `hostname1`, is a default (placeholder) name. You must modify the default host name (`hostname1`) by replacing it with the actual name of the license server host machine.

*host\_ID* (not user modifiable)

This is the host ID of the machine to be used as the server. This is the value you communicated to Synopsys before receiving your license key file.

If you receive a license key file generated for an incorrect host ID, contact your sales representative.

**Caution:**

Do not change the host ID value because it is used in the license key encryption process. The host ID value in the license key file must match the host ID value of the physical machine as determined by the `lmhostid` command; otherwise the license key file is invalid.

The host ID of the server specified in the example `SERVER` line is `8099fadc`. For details on the host ID, see Chapter 4, “[Downloading SCL Software and Obtaining License Key Files](#).”

*port\_number* (user modifiable)

The TCP port number used by the `lmgrd` daemon.

For the example `SERVER` line, the TCP port number for the `lmgrd` daemon running on that server uses the default value of 27000. Valid values are between 1024 and 64000 inclusive.

## The `VENDOR` Line

SCL uses the `VENDOR` line to identify the location of the `snpslmd` vendor daemon. (In other licensing systems based on FLEXnet, this line might be called a `DAEMON` line.)

Here is the `VENDOR` line in the license key file shown in [Example 7-3 on page 7-9](#):

```
VENDOR snpslmd /path/to/snpslmd 27000
```

The `VENDOR` line specifies the following information:

```
VENDOR daemon_name daemon_path {options_file_path} \  
      {port=tcp_port}
```

*daemon\_name* (not user modifiable)

This is the name of the Synopsys vendor daemon, `snpslmd`.

Do not modify this value.

*daemon\_path* (user modifiable)

This is the path to the Synopsys `snpslmd` daemon.

*options\_file\_path* ()

This is the fully qualified path to the options file used by the Synopsys `snpslmd` daemon. (The license key file `VENDOR` line in [Example 7-3 on page 7-9](#) does not specify an options file path.)

Note:

If you require an options file, it is recommended that you specify the path to the options file. For example,

```
/path/to/snpslmd.opt
```

or

```
options=/path/to/snpslmd.opt
```

If you do not specify the path, the file must be named `snpslmd.opt` and must reside in the same directory as the license key file.

*tcp\_port* (optional)

This is the fixed TCP port number for the vendor daemon to use, (for example, `port=27011`). This port, if specified, must be different than the port specified on the `SERVER` line.

Set this optional value only if clients need to connect to the license server from outside the firewall. (Many Internet firewalls require that internal port numbers accessed from outside the firewall be specified.)

In the license key file shown in [“Synopsys License Key File Example” on page 7-9](#), the `VENDOR` line does not specify a TCP port number for the `snpslmd` daemon. Therefore, the TCP port number to be used by `snpslmd` will be determined randomly.

---

## The `USE_SERVER` Line

By default, every Synopsys license key file includes a `USE_SERVER` keyword after the `VENDOR` line. Do not remove this keyword. The `USE_SERVER` line prevents client applications from reading the license file and forces them to request their licenses by network calls to the server specified on the `SERVER` line.

Here is the `USE_SERVER` line from the license key file shown in [Example 7-3 on page 7-9](#):

```
USE_SERVER (keyword)
```

---

## The License Key File INCREMENT Line

The INCREMENT line defines the licenses (features) that are included with a product.

Here is an INCREMENT line from [Example 7-3 on page 7-9](#):

```
INCREMENT PrimeTime snpslmd 2009.12 31-dec-2010 8 \  
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=30-oct-2009 ISSUED=21-nov-2009 ck=4 \  
  SN=RK:2595-0:868738:325472 \  
  START=30-nov-2009  
  AUTH={ snpslmd=(LK=9D76D499C7EE3BAC14EF) }
```

The remainder of this section explains the fields comprising the INCREMENT line.

### Important:

The following fields cannot be modified.

#### *feature\_name*

The name of the feature to which the license pertains. In the previous example, PrimeTime is the feature.

#### *vendor\_daemon*

The name of the vendor daemon. For SCL, the vendor daemon is always `snpslmd`.

#### *version*

The version number of the feature supported by this license. The previous example specifies a license for version D-2009.12 of PrimeTime. (The version field is typically in date format, where 2009 corresponds to the year of the tool release and 12 to the twelfth month of the year.)

#### *exp\_date*

The date when the specified license expires. In the example, the PrimeTime license expires on December 31, 2010 (31-dec-2010).

#### *number\_of\_licenses*

The number of concurrent licenses for the feature. In the example, nine licenses of PrimeTime can be concurrently checked out.

#### VENDOR\_STRING

The `VENDOR_STRING` in the example INCREMENT line has a value of `^1+S`, indicating that the PrimeTime feature is on support. This string is present only in on-support keys and provides forward-compatibility for most Synopsys products. Synplicity products do not use the On-Support functionality.

For details about on-support keys, see [“On-Support Keys” on page 7-8](#).

**SUPERSEDE**

Specifies that all licenses issued before the date specified by the `ISSUED` field are superseded by this line and invalidated. For details about `SUPERSEDE`, see [“SUPERSEDE Keys” on page 7-8](#).

**ISSUED**

The date the license was issued. The example license for PrimeTime was issued on November 21, 2009 (`ISSUED=21-nov-2009`).

**ck**

This is a checksum field [`ck=nnn`] but is no longer used.

**SN**

The `SN` (serial number) string contains various subfields.

The first subfield is set to one of these values:

- `RK` (revenue key) denotes a technology subscription license.
- `PK` (peak key) denotes a monthly technology subscription license key.
- `TK` (temporary key)

The serial number for the PrimeTime license key shown in the previous example is `SN=RK:2595-0:868738:325472`. In this example, the first subfield is set to `RK`.

The second subfield is the material number, which represents the product that this feature belongs to. In the example, the material number is `2595-0`, which corresponds to the product PrimeTime.

The third subfield is a security field.

**START**

The explicitly specified date when the license can first be used. For the example `INCREMENT` line, the start date for use of the PrimeTime license is November 30, 2009 (`START=3-nov-2009`).

**AUTH**

This field contains a list of supported daemons as well as encryption information. In the example key, the `AUTH` field looks like this:

```
AUTH={ snpslmd=(LK=9D76D499C7EE3BAC14EF) }
```

This means that this key supports clients (tools) built only on the `snpslmd` daemon. The `LK=` fields contain encryption information.

---

## On-Support Keys

On-support keys are licenses that contain the string `VENDOR_STRING=^1+S`. On-support licenses provide continuous support for product releases up to two years beyond the version specified in the version field. The advantage of on-support licenses is that you do not need to upgrade your license file for every new release.

Synplicity products do not use the on-support functionality.

Consider the following INCREMENT line for the Design-Compiler feature shown in [Example 7-1](#).

### Example 7-1 On-Support License Example

```
INCREMENT Design-Compiler snpslmd 2007.12 31-dec-2010 9 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=09-jan-2007 \
  ck=50 SN=RK:2661-0:668133:325472 START=1-mar-2007 \
  AUTH={ snpslmd=( LK=5D86A4B97689DA46C550) }
```

This on-support license is valid for Design Compiler versions through D-2009.12, which is later than the one specified in the version field (2007.12). The license is not valid for versions after D-2009.12. Note that this key cannot be used after the expiration date of December 31, 2010.

If this license did not have the on-support string (`VENDOR_STRING=^1+S`), you could not use a later version of Design Compiler, such as B-2009.06.

---

## SUPERSEDE Keys

SUPERSEDE keys have a special `SUPERSEDE` field. SUPERSEDE keys void all licenses (with the same feature names) that have an issue date earlier than the SUPERSEDE key's `ISSUED` date.

Consider the SUPERSEDE keys license file in [Example 7-2](#):

### Example 7-2 SUPERSEDE Keys License File Example

```
INCREMENT PrimeTime snpslmd 2009.12 31-dec-2010 8 VENDOR_STRING=^1+S \
  SUPERSEDE ISSUED=30-oct-2009 ck=4 SN=RK:2595-0:868738:325472 \
  SN=RK:2595-0:868738:325472 \
  START=30-nov-2009 AUTH={ snpslmd=( \
  LK=9D76D499C7EE3BAC14EF) }

INCREMENT PrimeTime snpslmd 2009.12 07-mar-2010 2 VENDOR_STRING=^1+S \
  ISSUED=07-sep-2009 ck=4 SN=TK:2595-0:0:211426:517493 \
  START=07-sep-2009 AUTH={ snpslmd=( LK=9D76D499C7EE3BAC14EF) }
```

**Example 7-2** includes two PrimeTime keys (INCREMENT lines), comprising one revenue (technology subscription license) key (SN=RK) and one temporary key (SN=TK). These keys have a total of 10 seats (8 + 2).

The first PrimeTime key has a SUPERSEDE field and an issue date of October 30, 2009. This key voids any PrimeTime keys issued prior to that date. Because the second PrimeTime key has an earlier issue date (ISSUED=07-sep-2009), it is voided. Therefore, only 8 seats of PrimeTime are available.

All license keys for technology subscription licenses include the SUPERSEDE keyword. Typically, temporary licenses and temporary licenses do not include SUPERSEDE.

---

## Synopsys Example License File

**Example 7-3** shows a typical license key file in the format delivered by Synopsys. The sample file includes on-support technology subscription licenses, an on-support perpetual (20-year) license, and an on-support monthly technology subscription (peak) license. (This example does not include any temporary licenses because they are not delivered by SmartKeys.)

### Example 7-3 Synopsys License Key File Example

```
#Synopsys License file created by CVDKIF 3.4.10.1 on October 28, 2009 at 19:55:09 for
daemon snpslmd
  SERVER hostname 829ED4A0 27000
  VENDOR snpslmd /path/to/snpslmd
  USE_SERVER

INCREMENT SSS snpslmd 1.0 05-Oct-2025 1 B2135255BFE7 \
  VENDOR_STRING="eb89e 9fafb 8be2c 9030a 38ed3 0d014 db251 6ffeb90b1cf95" \
  NOTICE="Licensed to Synopsys, Inc. [DO NOT DELETE THIS SSS KEY]" \
  SN=RK:0:0:325472 ISSUER="Synopsys Inc." START=18-Jul-2002 }

INCREMENT DesignWare snpslmd 2009.12 31-dec-2010 1 VENDOR_STRING=^1+S \
  SUPERSEDE ISSUED=21-jun-2008 ck=253 SN=PK:2925-0:847487:9396:475084\
  START=30-nov-2009 AUTH={ snpslmd=(LK=1D1675154904BAC87FBD) }

INCREMENT DesignWare snpslmd 2009.12 31-dec-2010 2 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2008 ck=252 \
  SN=RK:2925-0:868730:325472 START=30-nov-2009 \
  AUTH={ snpslmd=(LK=CD4664E94E6462682FFD) }

INCREMENT DB-Mode snpslmd 2009.12 31-dec-2010 10 VENDOR_STRING=^1+S \
  SUPERSEDE ISSUED=16-nov-2008 ck=22 SN=RK:206337:189074 \
  START=16-mar-2009 AUTH={ snpslmd=( LK=CDC6205CCC510516D36E) }

INCREMENT spice_check snpslmd 2009.12 31-dec-2010 10 \
  ISSUED=16-nov-2008 ck=239 SN=RK:223560:534994 \
  START=16-nov-2008 AUTH={ snpslmd=( LK=ADB75301FC0002193394) \
  sandwork=( SIGN=3EF87D9E300AE9C6) }

INCREMENT chipit_hcdebug_iridium snpslmd 2009.12 31-dec-201010 \
```

```

ISSUED=28-jan-2009 ck=52 SN=RK:248592:906528 \
START=28-jan-2009 AUTH={ pdld=( SIGN="12DB \
47F5 AC68 EACB 7572 4620 D6ED 8D0E 840E 4C29 727B 862F 3406 \
929A C0C5 06BF 6009 2DDF 76B8 6D43 878A 2596 1DE3 762F C637 \
590D 1ECF 0A1C D07F 8F5A") snpslmd=( LK=3DCA919C4E615986C742) }

INCREMENT Formality snpslmd 2009.12 31-dec-2010 2 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 \
ck=235 SN=RK:2593-0:868731:325472 START=31-jan-1998 \
AUTH={ snpslmd=( LK=BD060419EAC935620CE5) \
synopsysd=( LK=9D46A49985614122D3F6) }

INCREMENT Formality-E1 snpslmd 2009.12 31-dec-2010 2 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 ck=46 \
SN=RK:2593-0:868731:325472 START=31-jan-1998 \
AUTH={ snpslmd=( LK=AD36F4F926AD783DC553) \
synopsysd=( LK=9DB6D48931588E6D8556) }

INCREMENT PrimeTime snpslmd 2009.12 31-dec-2010 8 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 \
ck=4 SN=RK:2595-0:868738:325472 START=30-nov-2009\
AUTH={ snpslmd=( LK=9D76D499C7EE3BAC14EF) }

INCREMENT hspice snpslmd 2009.12 31-dec-2010 32 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 \
ck=50 SN=RK:6719-0:868733:325472 START=30-nov-2009\
AUTH={ snpslmd=( LK=5D86A4B97689DA46C550) \
avantd=( LK=8DB6A4B9820FC454A318) }

INCREMENT hspiceva snpslmd 2009.12 31-dec-2010 32 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 \
ck=128 SN=RK:6719-0:868733:325472 START=30-nov-2009\
AUTH={ snpslmd=( LK=3D76F4496C6D4D59F41F) \
avantd=( LK=9DE6C4A90DD695C41E0C) }

INCREMENT metawaves snpslmd 2009.12 31-dec-2010 32 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=21-jun-2009 \
ck=247 SN=RK:6719-0:868733:325472 START=30-nov-2009\
AUTH={ snpslmd=( LK=2D5694F9BBEAF2479700) \
avantd=( LK=6D06641964A4A04CC5D0) }

INCREMENT identdebugger snpslmd 2010.12 31-dec-2010 2 \
VENDOR_STRING=fpga SUPERSEDE ISSUED=01-jan-2009 ck=159 \
SN=RK:4842-0:1067383:810881 START=01-Jun-2009 AUTH={ \
synplctyd=( SIGN="02CD 753D C08C 8886 1AB2 940F 5E95 210D 5730 \
AEF6 8F02 6BA3 50A0 9661 0A34 199D 4914 6598 BCA5 073C E214") }

INCREMENT synplify snpslmd 2010.12 31-dec-2010 4 \
VENDOR_STRING=fpga SUPERSEDE ISSUED=01-jan-2009 ck=131 \
SN=RK:4879-0:1067382:810881 START=01-Jun-2009 AUTH={ \
synplctyd=( SIGN="0180 F773 0223 7569 C167 B7FB 26AB 9080 C9FB \
526A B303 954C 79BE 0BB8 684F 7349 D66A C9C7 897E 87C5 E87C") }

#-----

```

# 8

## Maintaining Synopsys Common Licensing

---

This chapter describes how to maintain the SCL licensing software when you change the host system used as the license server, add new license servers (rehosting), or obtain new license key files.

This chapter includes these sections:

- [Maintaining Synopsys Common Licensing](#)
- [SCL License Key File Verification Checklist](#)
- [Procedure to Update a Synopsys License File](#)
- [License Expiration Alert](#)

---

## Maintaining Synopsys Common Licensing

Over time, your licensing system and network will undergo changes. For example, you might change the machines you use to host your license servers or you might add servers. Most likely, you will change the number or kind of licenses you use. This section explains related tasks.

Here are the most common tasks you perform in maintaining your SCL licensing system:

- Adding monthly technology subscription licenses. When you request redemption of a monthly technology subscription license, you are sent an e-mail message containing that license. You can add this license to your license key file by using any text editor.
- Rehosting. Whenever you change the host machine used as your license server, you must “rehost” the system. This process entails obtaining a rehost form from your sales representative and using this form to communicate the licenses to be moved as well as the host IDs of the new server. Only licenses that are on maintenance (on support) can be rehosted.
- Retrieving license keys. When you retrieve your license keys for a site ID using Smartkeys, the license key file will contain the full complement of active licenses for that site, including
  - Newly purchased term licenses
  - Previously issued and active term licenses
  - Previously redeemed and active monthly technology subscription licenses

SmartKeys maintains the current state of your license key file and always returns the superset of active licenses, eliminating any expired or off-support licenses. You must entirely replace your old license key file with the new one. Only temporary licenses can be added to the license key file. Adding any other licenses will void the entire file.

**Important:**

Any time features are added or removed in the license key file, run the `sssverify` utility on the key file before restarting the license server to ensure license key file integrity.

---

## SCL License Key File Verification Checklist

To avoid unpredictable license daemon behavior and license denials, follow these guidelines:

- Use the complete license file as received from Synopsys or as retrieved from the SmartKeys system. You must not add, delete or modify any INCREMENT lines within the license file. As new transactions occur (maintenance renewals, remixes, updates, rehosts, and so on), the entire license file is regenerated and again must be used without any modifications.
- If you receive temporary or monthly technology subscription license keys from Synopsys, you can append them to the existing revenue license file. These keys must have an issue date equal to or greater than the issue date of the on-support revenue keys with the same feature name (check the ISSUED field of the license key file).
- It is strongly recommended that you use a separate license server for temporary or monthly technology subscription license keys. This helps to ensure that these keys are not invalidated by subsequent revenue keys with a later issued date.

---

## Validating New SCL Key Files

When you receive a new Synopsys license key file by e-mail or through the SmartKeys system, you must run the `sssverify` utility before using the new key file. Run the `sssverify` utility on the license file to identify any errors before starting the server. To use the file, enter

```
% scl_root/platform/bin sssverify /path/to/synopsys.lic
```

You must also use this utility whenever the license file is updated. The `sssverify` utility authenticates the integrity of the license file and detects any formatting errors in the file.

To start `sssverify`, enter

```
% sssverify license_file
```

If you receive a license error message, such as “License file integrity check failed!,” see [“Using sssverify to Troubleshoot a Synopsys License File” on page 9-10](#).

---

## Validating Existing or New SCL License Files

All regular (release) keys must have a valid `sss` key. A missing or invalid `sss` key makes the license file invalid and can result in unpredictable license daemon behavior.

As a precaution, check your SCL license debug log file for `sss` errors. For example, an `sss` warning from a debug log file without a valid `sss` key is shown here:

```
12:54:03 (snpslmd) WARNING: SSS errors.  
12:54:03 (snpslmd) Use the sssverify utility to check the  
    integrity of your license file.  
12:54:03 (snpslmd) The license file should be used exactly  
    as received from Synopsys.
```

**Important:**

If the license server log file includes the previous error message, this indicates that the file is corrupt. You must rectify the error messages by invoking the `sssverify` utility before you proceed. If the problem is not corrected, the license server might behave erratically and users might see random license denials. For troubleshooting details about `sssverify`, see [“Using sssverify to Troubleshoot a Synopsys License File” on page 9-10](#).

If you encounter this type of error in your file, retrieve the latest key file from SmartKeys at <http://www.synopsys.com/smartkeys>

---

## Procedure to Update a Synopsys License File

Typically, when your current license file is about to expire, you will receive a new license file from Synopsys. Whether you received an updated license file or not, you can always retrieve your latest keys from Smartkeys (see [“Logging In to SmartKeys” on page 4-3](#)).

If you are replacing an existing license file that is currently running under SCL, use the following instructions, depending on your scenario:

- Scenario 1– New license file dates overlap the expiration dates of the existing, about-to-expire license file.
- Scenario 2 – New license file dates do not overlap the expiration dates of the existing, about-to-expire license file.

### Scenario 1

In this scenario, the new license key file dates overlap with the existing, about-to-expire license file. For example, assume that your current license file expires on December 1, 2009, and the new license file has a start date of November 30, 2009. To update your license key file on or after the start date of the new license file, follow these steps:

1. Make sure that you have the latest version of Synopsys Common Licensing (SCL) installed. To download the latest version of SCL, go to the Download Center at <https://solvnet.synopsys.com/DownloadCenter/dc/product.jsp>
2. Verify the accuracy of the new license file by using the `sssverify` utility, which is included with SCL. Use the following syntax:

```
% cd scl_root/platform/bin  
% sssverify /path/to/license/file
```

3. Rename the `synopsys.lic` file to the file name `synopsys.lic.old`.
4. Rename the new license file to the file name `synopsys.lic`.
5. Make sure that the host name, port number, and vendor daemon path information are correct. To ensure that no user jobs are disconnected from the license server, copy the `SERVER` and `VENDOR` lines from the old key file. The `VENDOR` path information can change, but only if you are upgrading to a new version of SCL.
6. Do not add any keys (`INCREMENT` lines) to the new license file unless they are temporary keys that are issued after the new license file was issued. (To determine whether they are temporary, you can compare the `ISSUED` date fields.)
7. Use the `lmdown` command to stop the current license daemon.
8. Make sure the `lmgrd` and `snpslmd` processes are no longer running. Also verify that all Synopsys lock files for `snpslmd`, `avantd`, `tmald`, `nassd` and so forth are removed from the `/usr/tmp` directory. For example, remove files such as `locksnpsslmd`, `lockavantd`, `locktmald`, `locknassd`.
9. Restart the SCL license server by using the `lmgrd` command.  
Important: You should not use the `lmreread` command when you are replacing an entire keyfile.
10. Check the debug log file to make sure the server has started correctly.

## Scenario 2

1. Verify the accuracy of the new license file by using the `sssverify` utility, which is included with SCL. The syntax is the following:  

```
% cd scl_root/platform/bin
% sssverify /path/to/license/file
```
2. Rename the `synopsys.lic` file to the file name `synopsys.lic.old`.
3. Rename the new license file to the file name `synopsys.lic`.
4. Make sure that the host name, port number, and vendor daemon path information are correct. This information must be the same as that for the `synopsys.lic.old` file. To ensure accuracy, copy the `SERVER` and `VENDOR` lines from the old key file.
5. Do not restart the server by using the `lmgrd` command. Do not use `lmreread`. The server automatically rereads the license file, which is renamed to the old license file, at 12:00 midnight the next day, when the keys from the old license file expire.
6. Sometime after midnight the next day, verify that the keys have started.
7. Check the debug log file to make sure the server has started correctly.

---

## License Expiration Alert

The `SCL_DISPLAY_EXPIRE` and `SCL_DAYS_EXPIRE` variables issue warning messages to notify license administrators of impending license feature expiration. The warnings are displayed in the debug log file.

---

### SCL\_DISPLAY\_EXPIRE

The `SCL_DISPLAY_EXPIRE` variable allows you to set the frequency of your license expiration warning messages in minutes.

#### Syntax

```
setenv SCL_DISPLAY_EXPIRE minutes
```

where *minutes* is the number of minutes between license expiration warnings.

---

### SCL\_DAYS\_EXPIRE

The `SCL_DAYS_EXPIRE` variable allows you to specify how soon before the license expiration date the warning messages should start.

#### Syntax

```
setenv SCL_DAYS_EXPIRE days
```

where *days* is the number of days before the license expiration that you want the warning messages to start.

#### Example

```
% setenv SCL_DISPLAY_EXPIRE 10  
% setenv SCL_DAYS_EXPIRE 30
```

These settings cause warning messages to begin 30 days before expiration, at a frequency of 10-minute intervals.

The following example shows a warning message printed in the debug log. The message shows the feature name, the feature key, and the expiration date.

```
15:29:58 (snpslmd) EXPIRATION WARNING: f3 07EB8A0EC08C Sep-25-2010
```

#### Note:

If you do not set a value for *days*, warning messages begin 14 days before expiration, but only when the server is started or reread.

# 9

## Identifying and Resolving Problems

---

This chapter explains some common problems you might encounter in configuring and running SCL software, including problems in starting up the license server and problems encountered by users attempting to acquire licenses.

- [Common Problems](#)
- [Mapping SCL Error Messages to FLEXnet Error Codes](#)
- [Error Conditions: Possible Causes and Solutions](#)
- [Troubleshooting](#)
- [Known Issues](#)

---

## Common Problems

The two most common problems you might encounter in running SCL are the inability to start the license server and the inability to check out licenses. The following sections explore some of the reasons these problems might occur:

- [Determining Why You Cannot Start the Server](#)
- [Diagnosing Why You Cannot Check Out a License](#)

---

### Determining Why You Cannot Start the Server

If you cannot start the license server, the most important step in debugging is to look at the debug log file. This file shows specific errors. It also shows the FLEXnet version of `lmgrd` and `snpslmd`, as well as the SCL version. Both the FLEXnet version of `lmgrd` and `snpslmd` must be 11.6.1 or later. Make sure these versions are correct.

General things to look for in the license key file:

- Verify that the license file has read permissions.
- Verify the integrity of the license key file by using the `sssverify` utility. For more information about `sssverify`, see [“Checking the Integrity of the License File” on page 3-2](#).
- Verify that the host ID specified on the `SERVER` line is correct and matches the results of `lmhostid`. (This number cannot be changed.)
- Verify that the `SERVER` name is correct and that you are logged into this server.
- Verify that the `VENDOR` line specifies the correct path to `snpslmd`.

For details on what to look for in the file, see [“Checking Requisite License Key File Content: SERVER and VENDOR Lines” on page 9-23](#).

Other things to look for:

- Make sure you used the correct syntax to start `lmgrd` and that the license key file (`synopsys.lic`) is in the location specified.

The basic syntax is

```
lmgrd -c synopsys.lic -l debug.log
```

- Use the `lmdown` utility to stop previous instances of SCL (`lmgrd` and `snpslmd`).
- On UNIX, use the `ps` command to verify that all instances of the `snpslmd` daemon have been stopped, as well as the parent `lmgrd` process.

- Make sure that you are not running any legacy daemons. For a list of legacy daemons, see [“Synopsys Legacy Vendor Daemons” on page 1-5](#).
- On UNIX, check the `/usr/tmp` directory and remove any lock files (lock\*) for `snpslmd` and `legacy` daemons. (See [Table 1-2 on page 1-5](#) for a list of Synopsys legacy daemons.)

---

## Diagnosing Why You Cannot Check Out a License

When you cannot check out a license for a supported feature, you can run diagnostic utilities such as `lmstat` or `lmdiag` to help identify the source of the problem. For information on these utilities, see [“Using lmdiag and lmstat to Diagnose Problems When You Cannot Check Out a License” on page 9-24](#).

If `lmstat` or `lmdiag` cannot contact the server, verify that the `snpslmd` daemon is running on the server node.

Next, you should ensure that there are no problems in the following areas:

- Verify that the license environment variables are set correctly on the client attempting to check out the license. Ensure that the license environment variable points to the server whose license key file contains the license for the required feature. For information on setting environment variables, see [“Describing the License Environment Variables” on page 6-4](#).
- If you are using an older tool version, run the `whatscl` utility to make sure the tool is compatible with SCL. (Make sure to specify the actual binary file, typically in an OS platform directory, and not a text script.) For tools that include SCL code, this utility returns the SCL version of the tool. For legacy tool versions, nothing is returned.

**Note:**

The `whatscl` utility does not return anything for Synplicity products, even if they are SCL compliant.

If the tool is a legacy application, it might still be compatible with SCL. See [“Legacy Application Compatibility With SCL” on page 2-8](#), or contact your local Synopsys Support Center.

- Use the `sssverify` utility to validate the integrity of the license file and detect any errors in the file. It is mandatory to use the complete combined vendor daemon license file as received from Synopsys. The license file should not be edited or merged with other license files. For more information about `sssverify`, see [“Verifying the Content and Integrity of the License Key File” on page 9-23](#).
- Verify that you can connect to the server. Use any TCP-based command, such as `telnet`, to connect to the server. If the system hosting the server is down when the client first attempts to obtain a license, the reported message might indicate that no licenses are available.

- Verify that there are no network connectivity or communications problems between the client and the server. SCL general messages reporting that a license is not available could also indicate a network connection problem. The message would not identify this explicitly as the source of the problem, but you should check for the condition.

---

## Mapping SCL Error Messages to FLEXnet Error Codes

[Table 9-1](#) contains some of the most commonly encountered error conditions. It lists the FLEXnet error code for an error condition, the corresponding Synopsys product-specific licensing error message displayed to a user, and one or more notations indicating corresponding causes and solutions. Corresponding causes and solutions are explained separately from individual error messages because they might apply to many different error conditions and reported error messages.

For an explanation of corresponding causes and solutions indicated by the notations, see [“Causes” on page 9-7](#) and [“Solutions” on page 9-8](#).

*Table 9-1 Mapping FLEXnet Error Codes to SCL Error Messages and Causes*

<b>FLEXnet error code and meaning</b>	<b>SCL product-specific equivalent error messages</b>	<b>Corresponding causes and solutions</b>
-1 (LM_NOCONFFILE) Cannot find license key file.	SEC-2: Cannot open key file <i>filename</i> .	C12, C14 S13
-2 (LM_BADFILE) Invalid license key file syntax.	or	
-30 (LM_NOREADLIC) Cannot read license key file.	A licensing environment parameter has not been set correctly.	
-8 (LM_BADCODE) Invalid (inconsistent) license key. The license key and data for a feature do not match. This usually happens when a license file has been altered.	SEC-10: Software is not licensed for this machine.	C1, C3, C4, C5, C6 S1, S2, S3, S4
-9 (LM_NOTTHISHOST) Invalid host. The host ID of this system does not match the host ID specified in the license file.		
- 31 (LM_TOOEARLY) Feature start date is in the future.	SEC-11: Software is not yet enabled or has expired.	C3, C4 S2, S3

Table 9-1 Mapping FLEXnet Error Codes to SCL Error Messages and Causes (Continued)

FLEXnet error code and meaning	SCL product-specific equivalent error messages	Corresponding causes and solutions
-3 (LM_NOSEVER) No server for this feature.	SEC-12: Can't communicate with the license server.	C8, C9, C10, C11, C12 S8, S9, S10, S11
-15 (LM_CANTCONNECT) Can't connect to license server: <ul style="list-style-type: none"> <li>- The lmgrd server has not been started yet.</li> <li>- The wrong <i>port@host</i> or license file is being used.</li> <li>- The port or host name in the license file has changed.</li> </ul>	SEC-12: Can't communicate with the license server.	See <a href="#">"What Happens When the License Server Goes Down"</a> on page 9-23.
-29 (LM_CANTFINDETHER) Cannot find Ethernet device.	SEC-12: Can't communicate with the license server.	C8, C9, C10, C11, C12 S8, S9, S10, S11
-34 (LM_CLOCKBAD) Clock difference is too large between client and server.	SEC-13: The date/time difference between the client and the license server host is too great.	C16, S15
-11 (LM_BADDATE) Invalid date format in the license file.	SEC-14: Key file syntax error: <i>@keyfile_name</i> .	C1, S1, S2
-13 (LM_NO_SERVER_IN_FILE) No SERVER lines in license file.	SEC-12: Can't communicate with the license server.	C8, C9, C10, C11, C12 S8, S9, S10, S11
-14 (LM_BADHOS) Cannot find SERVER host name in network database. The lookup for the host name on the SERVER line in the license key file failed. This often happens when NIS or DNS or the hosts file is incorrect. As a workaround, use the IP address instead of host name.	SEC-12: Can't communicate with the license server.	C8, C9, C10, C11, C12 S8, S9, S10, S11
-4 (LM_MAXUSERS) Licensed number of users already reached.	SEC-50: All feature_name licenses are in use.	C6, S6
-24 (LM_USERSQUEUED) Users are queued for this feature.	SEC-50: All feature_name licenses are in use.	C6, S6

Table 9-1 Mapping FLEXnet Error Codes to SCL Error Messages and Causes (Continued)

FLEXnet error code and meaning	SCL product-specific equivalent error messages	Corresponding causes and solutions
-5 (LM_NOFEATURE) No such feature exists. -25 (LM_SERVERLONGGONE) License server does not support this version of this feature. -21 (LM_OLDVER) License file does not support this version.	SEC-51: This site is not licensed for <i>feature_name</i> .	C4, S2, S3, S6, S9
-26 (LM_TOOMANY) Request for more licenses than this feature supports.	SEC-52: Requested more licenses for <i>feature_name</i> than supported in the key file.	C3, S3
-38 (LM_FEATEXCLUDE) User/host on EXCLUDE list for feature.	SEC-53: The end-user license options EXCLUDE you from using <i>feature_name</i> .	C7, S16
-39 (LM_FEATNOTINCLUDE) User/host not on INCLUDE list for this feature.	SEC-54: The end-user license options don't INCLUDE you for using <i>feature_name</i> .	C7, S16
-23 (LM_BUSYNEWSERV) License server temporarily busy (new server connecting).	SEC-82: License server is busy, retrying.	C16
-12 (LM_BADCOMM) Invalid returned data from license server.	SEC-85: Communication with the license server failed.	C9, C10, C11 S10, S11, S12, S13
-16 (LM_CANTREAD) Cannot read data from license server.		
-17 (LM_CANTWRITE) Cannot write data to license server.		
-22 (LM_CHECKINBAD) Feature checkin failure detected at license server.		

---

## Error Conditions: Possible Causes and Solutions

This section presents the most common causes of error conditions, the symptoms they present, and the ways to resolve the problems. Here is how this information is organized:

- Each possible cause is labeled with the letter C (for cause) followed by a number.
- Each possible solution is labeled with the letter S (for solution) followed by a number.

Causes and solutions are referred to by their labels from various entries documenting error messages in [Table 9-1 on page 9-4](#).

---

### Causes

- C1. The INCREMENT line for the license key entry is corrupt or the INCREMENT line for the license has been modified, which invalidates the entire line, and thus, the license key file.
- C2. The license has expired.
- C3. The start date for the license has not yet occurred.
- C4. Licenses are not provided for the requested feature on any of the specified servers.
- C5. There are no licenses for the version of the feature requested.
- C6. The license daemon located one or more licenses for the requested feature on one of the specified license servers, but all licenses are in use.
- C7. The user requesting the feature has been excluded from access to a license for this feature or has not been explicitly granted access.
- C8. The VENDOR line in the license key file might include specification of an invalid path to the `snpslmd` daemon, or the VENDOR line specifies an options file and path without specifying the `options=` keyword. In this case, the single path specification on the VENDOR line is interpreted to be that of the `snpslmd` daemon.
- C9. The `lmgrd` and `snpslmd` daemon versions are incompatible. The version of the `lmgrd` daemon that is running is less than the version of the `snpslmd` daemon. If the `lmgrd` daemon is not equal to or greater than the version of the `snpslmd` daemon, results are unpredictable.
- C10. The `snpslmd` binary has been corrupted.
- C11. The tool (application program) is referencing the wrong license key file.
- C12. The license key file was modified; perhaps the host ID on the SERVER line was modified or an INCREMENT line was modified.

- C13. The license environment variable is set incorrectly.
- C14. The license key file is not in the specified location.
- C15. The permissions on the license key file render it unreadable by the SCL daemons.
- C16. The date or time value has been modified.
- C17. The license server is busy.

---

## Solutions

- S1. Check the INCREMENT line for the license to ensure that it contains all the required fields and that all lines but the last are terminated with a continuation character.
- S2. If you are on support for this feature or have purchased a new license for the feature but have not yet retrieved the key, see Chapter 4, “[Downloading SCL Software and Obtaining License Key Files](#),” for details on how to obtain it.

If you have not purchased a new license for the feature, but want to do so, contact your sales representative.

- S3. If the license is not yet active, you must wait until the license is available to use the feature, or contact your sales representative to have the license reissued.
- S4. Check to determine if other license servers not specified by the client contain the requested feature or the version of the requested feature. If so, reconfigure the client to refer to that license server.
- S5. Use `sssverify` to check the license key file containing the license for the feature to ensure that the line has not been modified or corrupted.

If the license key entry for the feature is corrupt, obtain a new license key file from Synopsys. See Chapter 4, “[Downloading SCL Software and Obtaining License Key Files](#).”

- S6. Check to determine if another license server not specified by the client contains the requested feature or the version of the requested feature. If so, reconfigure the client to refer to that license server.
- S7. Check the VENDOR line in the license key file to ensure that if a path to `snpslmd` is specified, it is the correct one, and that if an options file path is specified, the `OPTIONS=` keyword is used.
- S8. Run the `lmdiag` utility to diagnose the source of the problem.
- S9. Verify that the tool is configured to reference the correct license key file.
- S10. Ensure that the `snpslmd` daemon is running.

If you suspect that the `snpslmd` binary has been corrupted through a system failure or otherwise, replace the binary with the one in the original installation directory.

- S11. Obtain a new version of the license key file. For information on how to do this, see Chapter 4 “[Downloading SCL Software and Obtaining License Key Files.](#)”
- S12. Set the license environment variables correctly to refer to the license key file for the target license server.
- S13. Contact the Synopsys Technical Support Center for assistance. For information on ways to contact the Center, see “[Customer Support](#)” on page xiii.
- S14. Resolve the date or time conflict for the particular operating system.
- S15. Modify the options file to include the user (or remove the exclusion).

---

## Troubleshooting

This section provides some useful, high-level approaches to troubleshooting common problems.

---

### Determining Your Host ID by Using `lmhostid`

Use the FLEXnet `lmhostid` command, which is included with SCL, to determine a license server's host ID for any supported platform. For example, execute `lmhostid` or “`lmutil lmhostid`.” In the following example, the host ID of the machine is `833d63f3`:

```
% lmutil lmhostid
```

```
lmhostid - Copyright (C) 1989-2008 Acresso Software Inc. All Rights Reserved.  
The FLEXnet host ID of this machine is "833d63f3"
```

#### Note:

On Windows and Linux platforms, sometimes this command returns multiple values. You can choose any of these values, which correspond to the Ethernet, or MAC, address. Synopsys suggests that the 12-character Ethernet address that you submit for your license request match a physical network adapter on your machine. In some cases your computer might report the presence of a wireless device or virtual network adapter. Do not use one of these addresses for your host ID; they might not be reliable and can change unpredictably.

---

## Using sssverify to Troubleshoot a Synopsys License File

SCL uses Synopsys secure server (SSS) technology. It is important that any combined vendor daemon license files received from Synopsys be verified by running the `sssverify` tool. The failure to verify your license file can lead to license denials.

Use the following procedure to verifying a license file:

1. Make sure you have the latest version of SCL. Go to the Download Center at <https://solvnet.synopsys.com/DownloadCenter> for download instructions.
2. Make sure the license file host ID information is correct. Verify the host ID by using the `lmhostid` command. (SCL includes `lmhostid`.)
3. Examine the license file.
  - Make sure all comment lines start with a pound sign (#) and do not wrap.
  - All lines must start with a pound (#) sign or a keyword such as `SERVER`, `VENDOR`, `USE_SERVER`, `PACKAGE`, or `INCREMENT`.
  - `INCREMENT` lines can wrap only after a continuation character (\).
  - The `USE_SERVER` line must not be removed.
4. You must not add any keys (features or `INCREMENT` lines) to the license file, with the following exception:

For a given host ID, unexpired temporary keys with an `ISSUED` date equal to or later than the `ISSUED` date for the release keys can be added to the license file. Both short-term temporary keys (keys issued for more less than 60 days) and long-term temporary keys (keys issued for more than 60 days) require an SSST security key.

5. Run the `sssverify` utility:

```
% sssverify /path/to/synopsys.lic
```

Here is a sample output from running this utility:

```
Integrity check report for license file "license_file".
Report generated on 31-Oct-2009 (SCL_11.1)
-----
Checking the integrity of the license file....
Valid SSS feature found.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
License file integrity check PASSED.
-----
You may now USE this license file to start your license server.
Please do not edit or manipulate the contents of this license file.
```

As indicated in the message, using the license file is safe if there are no errors related to SSS.

**Note:**

If the license file contains only short-term temporary keys, you will get this warning message: “The SSS feature is invalid.” (However, the license file integrity check will still pass.) In this case, the warning can safely be ignored.

6. If you get an error message indicating that “License file integrity check failed,” download the latest license file from SmartKeys at <https://solvnet.synopsys.com/SmartKeys>, and run `sssverify` again.

The following examples show sample output from the `sssverify` utility. The message displayed depends on the condition of your license file. [Example 9-1](#) shows a validated license file.

**Note:**

If the `sssverify` utility reports that a license file is invalid, you must rectify the errors. If the problem is not corrected, the license server might behave erratically and users might see random license denials.

Note that all temporary license keys, including node-locked license keys, have the `SSST` feature in the license key file. In addition, all Monthly Technology Subscription License (MTSL) license keys (peak keys) include the `SSS` feature. A single SSS feature validates all peak revenue keys and other types of revenue keys.

A customer might receive a license key file that has either SSS, SSST, or both features in it. Customers should not attempt to modify or delete the SSST feature from the temporary license file. If there are multiple SSST features in their license files, the SSST features should be left as they are in the license file.

As with all license keys, any license key files received from Synopsys should be verified by running the SCL `sssverify` tool. A failure to verify the license file could lead to license denials. If you get any `sssverify` errors or any `SSS` errors in the license server log file, the tool issues license checkout request denials until the problem is resolved. For additional information about `sssverify`, see [“Using sssverify to Troubleshoot a Synopsys License File” on page 9-10](#).

**Example 9-1 Validated sssverify Command and Report**

```
% sssverify license_file
Integrity check report for license file "license_file".
Report generated on 31-Oct-2009 (SCL_11.1)
-----
Checking the integrity of the license file....
Valid SSS feature found.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
License file integrity check PASSED.
-----
You may now USE this license file to start your license server.
```

Please do not edit or manipulate the contents of this license file.

As indicated in this message, because no errors related to `SSS` violations are found, it is safe to use the license file.

If you have removed any features from the license file, you will see the message shown in [Example 9-2](#).

#### *Example 9-2 Invalid sssverify Command and Report: Removed Features*

```
% sssverify license_file
-----
Report generated on 31-Oct-2009
Checking the integrity of the license file...
Valid SSS feature found. INVALID license file fingerprint.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
3 features are missing from this file.
All revenue keys ("SN=RK:..." on feature line) have been excluded.
License file integrity check FAILED!
-----
This is an INVALID license file. You SHOULD NOT use this license file.
Please use the license file as received from Synopsys, Inc.
```

As indicated in the error message, the license file should not be used to start the license server.

If you have added any features to the license file, you will see the message shown in [Example 9-3](#).

#### *Example 9-3 Invalid sssverify Command and Report: Added Features*

```
% sssverify license_file
Integrity check report for license file "license_file".
Report generated on 31-Oct-2009 (SCL_11.1)
-----
Checking the integrity of the license file...
Valid SSS feature found. INVALID license file fingerprint.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
You have added 3 new features to this file.
All revenue keys ("SN=RK:..." on feature line) have been excluded.
License file integrity check FAILED!
-----
This is an INVALID license file. You SHOULD NOT use this license file.
Please use the license file as received from Synopsys, Inc.
```

As indicated in the error message, the license file should not be used to start the license server.

If the license server log file has `SSS` error messages, you will see the report shown in [Example 9-4](#).

**Example 9-4 Invalid sssverify Report: sss Errors**

```
% sssverify license_file
12:54:03 (snpslmd) WARNING: SSS errors.
12:54:03 (snpslmd) Use the sssverify utility to check the
integrity of your license file.
12:54:03 (snpslmd) The license file should be used exactly
as received from Synopsys
```

**Important:**

You should run `sssverify` on both short-term (keys with a duration of less than 60 days) and long-term temporary keys (keys with a duration of 60 days). All temporary license keys, including node-locked license keys, include the `SSST` feature in the key file. In addition, all Monthly Technology Subscription License (MTSL) keys (peak keys) include the `SSS` feature, so a single `SSS` feature validates all types of revenue keys.

When you run the `sssverify` utility on a key file, and the file contains neither the `SSS` nor the `SSST` feature, the message shown in [Example 9-5](#) should appear.

**Example 9-5 Running the sssverify Utility on a Key file**

```
=====
Integrity check report for license file "test.lic".
Report generated on 31-Oct-2009 SCL 11.1
-----

Checking the integrity of the license file...
No SSS or SSST features were found in the license file.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
All revenue keys ("SN=RK:..." on feature line) have been excluded.
License file integrity check FAILED!
-----

This is an INVALID license file. You SHOULD NOT use this license file.
Please use the license file as received from Synopsys, Inc.
=====
```

If the license file contains only the `SSS` but not the `SSST` feature, the message shown in [Example 9-6](#) should appear.

**Example 9-6 License File Containing SSS Feature but not SSST Feature**

```
=====
Integrity check report for license file "test.lic".
Report generated on 31-Oct-2009 SCL 11.1
-----

Checking the integrity of the license file...
Valid SSS feature found.
Siteid: 1001, Server Hostid: a956a4c, Issued on: 10/1/2009
No SSST key found.
SSST key is required to enable temp keys ("SN=TK:..." on feature line).
License file integrity check FAILED!
-----

This is an INVALID license file. You SHOULD NOT use this license file.
Please use the license file as received from Synopsys, Inc.
=====
```

The usual way to rectify `sssverify` problems is to download a new copy of the license key file from SmartKeys and run `sssverify` again.

If you are not able to rectify the error messages in the license file by invoking the `sssverify` utility, open a case with the Synopsys Support Center by going to <http://www.synopsys.com/support>

Alternately, you can call (800) 245-8005 or send e-mail to [support\\_center@synopsys.com](mailto:support_center@synopsys.com). If you are located outside North America, contact your local Synopsys Support Center.

---

## Determining Whether Your Tool Is Enabled for SCL

While starting the license server, you might encounter problems in which the sources are not obvious. In that case, it is a good idea to verify that the version of the tool you are running supports SCL. To determine if a tool supports SCL, use the `whatscl` utility, installed in the `scl_root/bin/platform` directory on UNIX systems and the `scl_root\bin\windows` directory on Windows systems.

If the product is enabled for SCL the, `whatscl` utility returns the version of SCL incorporated into the tool. (All versions of SCL code incorporated into Synopsys tools are compatible with the SCL 11.1 server.) For example, enter

```
% cd /synopsys/scl/linux/bin
% whatscl /synopsys/2009.03/hspice/linux/hspice
```

```
Synopsys Corporate Licensing (SCL) Release: version SCL_11.1,
Build 1; Label: SCL_11.1; Built on Sep 22 2009 at 23:41:36
```

### Note:

The `whatscl` utility does not return anything for Synplicity products, even if they are SCL compliant.

---

## Finding the Physical Location of the License File

To obtain the physical location of the license file, enter

```
% lmstat -c port@host
```

For example, if you are obtaining the license from `27000@server1`, use the following command on any machine in the same network:

```
% lmstat -c 27000@server1
```

```
lmstat - Copyright (c) 1989-2008 Acrecco Software Inc.
All Rights Reserved.
```

```
Flexible License Manager status on Sat 10/31/2009 09:57
License server status: 27000@server1
License file(s) on server1:
/synopsys/scl/synopsys.lic:
```

---

## Finding a List of All Tools Users

To retrieve a list of users, use `lmstat` with the `-a` option. Enter

```
% lmstat -c port@host -a
```

or

```
% lmstat -c /path/to/synopsys.lic -a
```

Make sure you do not point to more than one license server or file at a time.

---

## Checking the Daemon Versions for Compatibility

The version of the `lmgrd` daemon must be later than or equal to the version of the `snpslmd` daemon.

To check the version of `lmgrd`, enter

```
% lmgrd -v
```

To check the FLEXnet version of `snpslmd`, enter the following FLEX/*m* command:

```
% snpslmd -v
```

Note:

The FLEXnet version is different than the SCL version. To determine the SCL version, use the `whatscl` utility.

---

## System Monitoring Script

Use the `sysmon.sh` utility script included with SCL 11.1 to aid in identifying system or configuration issues that result in licensing errors. The `sysmon.sh` executable file and `sysmon.README.txt` file are included in the `scl_root/examples` directory.

On running the tool, this script collects a variety of information from the system and logs it into a file. The type of information collected includes the following:

- Hardware information (for example, number of CPUs, CPU speed, available RAM, and swap space)

- Network configuration (for example, TCP parameters and network interfaces)
- Network statistics (tcp and udp counters)

### Usage

Run the script in one of the following ways:

```
sysmon.sh -p port -s -r loopInterval [-l logfile]
```

or

```
sysmon.sh -p port [-l logfile]
```

Use the second command sequence to log the system state at any instant.

Here are the options:

-p

Specifies the `snpslmd` daemon port.

-s

Prints socket summary only. No other information is collected.

-r

Allows the script to run continuously, while periodically sampling the system state. The sampling value is in seconds.

-l logfile

Logs output to a user-defined file. The output of this file is saved under `/tmp` in the following format:

```
sysmon_DDMonYY:HHMM_$pid.log
```

Environment

Uses the `SNPSLMD_PATH` variable to locate FLEXnet binary files. The binary files are used to determine the release versions for `lmgrd` and the Synopsys daemon. The path should refer to the root installation directory and should contain `lmutil`, `lmgrd`, `snpslmd`, and `whatscl` binary files.

Supported Platforms

The following platforms are currently supported: Solaris, Linux (all systems), HP-UX, and AIX.

---

## Using the Debug Log File to Troubleshoot License Issues

The log file contains useful information to help you debug problems. When you start the `lmgrd` daemon to bring up the license server, be sure that you redirect the output into a log file (debug log) where you can examine it. To do this, use the `lmgrd` command with the `-l` log file switch. For example,

```
% lmgrd -c licensefile -l logfile
```

You must have write access to the directory containing the log file. The log file (as well as the license key file and other SCL components) should be locally mounted.

### Note:

You should have your debug log file at hand when you call the Synopsys Support Center.

[Example 6-1 on page 6-3](#) shows a sample log file report. The debug log file contains the following information:

- Start-up information
- SCL and FLEXnet version information  
The sample log file has FLEXnet version 11.6.1 and SCL version 11.1.
- TCP port information  
In the sample log file, the `lmgrd` license daemon uses TCP port 27000 and the `snpslmd` vendor daemon uses TCP port 39844.
- Security information  
In the sample log file, SCL reports that it has found a valid `sss` feature in the license key file.
- A list of incorporated daemons. SCL supports clients based on various daemons. A list of supported daemons incorporated into SCL is included in the log file. The list of incorporated daemons follows the “Serving features for the following vendor names” line.
- Informational messages  
In most cases, informational messages do not require intervention. These time-stamped messages identify license check-ins (IN:) and check-outs (OUT:) as well as license denials (DENIED:). They identify the user, client system, and feature, as well as other information.
- Error messages  
These messages identify configuration problems that require intervention. Problems such as the wrong host ID or an invalid host name are among the issues reported in this category. For example, messages might report that the daemon cannot open the options

file, that no `VENDOR` line in the file exists for a specified daemon, or the license key file is corrupt and, therefore, the daemon could not find licenses to serve. Common error messages are described in the following section.

---

## Common Error Messages Reported in the Debug Log File

This section explains some of the more common error messages recorded in the debug log file. (The debug log reports messages from the `lmgrd` and `snpslmd` daemons.)

- [SSS-Related Errors](#)
- [Other Messages and Resolutions](#)

### SSS-Related Errors

The errors in this section are related to the `sss` feature. Generally, to resolve `sss`-related errors, follow these steps:

- Do not add or remove keys from the license key file.
- Make sure you are running the latest version of SCL. The FLEXnet version for both `lmgrd` and `snpslmd` should be 11.6.1 or later. (FLEXnet and SCL version information are recorded in the debug log file.)
- Retrieve a new license file from SmartKeys.
- Run `sssverify` to verify the integrity of the license key file.

Specific `sss` (or `SSST`) error messages follow.

#### **“The SSS feature is missing. The SSS feature is invalid. This feature is required to enable other keys in your license file”**

This message is reported under the following conditions:

- The `sss` key is either missing or invalid, or `sssverify` indicates that the `INCREMENT` lines have errors.

#### **“Valid SSS feature found. Invalid License file fingerprint”**

The `sss` feature is valid but licenses have been added, removed, or altered.

#### **“You have removed 2 features from this file,” or “You have added 2 new feature to this file”**

This message is reported under the following condition:

- Features have been removed from or added to the license file.

**“Run sssverify utility to check the integrity of your license file. You should use the license file exactly as received from Synopsys”**

This message is reported under the following conditions:

- You are not using an authenticated Synopsys license file.
- You have removed or added features from the license file, which invalidates the license file.

**“All revenue keys (“SN=RK...” on feature line) have been excluded...The server is in an unstable state”**

This message is reported under the following conditions:

- The `sss` key is either missing or invalid.
- SCL indicates that the INCREMENT lines have errors.
- You have removed or added features from the license file, which invalidates the license file.

**“The following Temp Keys have been excluded...The server is in an unstable state”**

This message is reported under the following conditions:

- The `SSST` or (`sss`) key is either missing or invalid.
- SCL indicates that the INCREMENT lines have errors.
- You have removed or added features from the license file, which invalidates the license file.

## Other Messages and Resolutions

**“Not a valid server host name”**

The license server checks the host name on the SERVER line to ensure that you are running the license server on the correct host machine. This message is reported if you used an alias for the host in the license key file. The host name on the SERVER line must match the name displayed when you issue the `hostname` command.

**“Failed to open the TCP port number in the license”**

See [“Imgrd Error Message: Failed to open the TCP port number in the license” on page 9-29.](#)

**“Retrying socket bind (address already in use)”**

One cause of this problem is that SCL has been restarted but the operating system has not yet released the port. To resolve this issue, restart SCL with the `-reuseaddr` switch:

```
lmgrd -c synopsys.lic -l debug.log -reuseaddr
```

Another cause might be that another application is using the TCP/IP port number specified on the SERVER line of the license key file.

To resolve this problem, shut down the license server by using the `lmdown` utility. Then change the TCP port number in the license key file, restart the `lmgrd` daemon, and check the log file again.

**“lmgrd refused vendor name list. This daemon will only serve licenses for the primary vendor”**

This message is reported when a version of `lmgrd` is used that is not compatible with the `snpslmd` version. It is recommended that you use `lmgrd` and `snpslmd` only from the same SCL installation directory.

**“inconsistent authorization code”**

This error indicates that the host ID is not correct or that the keys are corrupt. Verify that SCL (`lmgrd`) was started on the correct license server and that the host ID is correct. Compare the host ID specified on the SERVER line with the results of the `lmhostid` command. If the keys are in error, contact your sales representative.

**“inconsistent encryption code”**

This message might be reported when a legacy version of the `snpslmd` vendor daemon is started. Check the debug log file to verify that SCL 11.1 or later has started. Make sure that the correct `snpslmd` path is specified in the VENDOR line of the license key file.

**“tcp\_s is bad”**

This error message is reported if you stop the previous instance of the license daemon and try to restart the daemon before the kernel releases the daemon port. The daemon reuses the port number—even if the kernel is temporarily holding the port.

This error occurs if all of the following conditions are present:

- The server is hosted on a Solaris operating system
- The VENDOR line has a `PORT=` keyword in the license file

To resolve this issue, you must use the `-reuseaddr` option while starting the license daemon to resolve this issue. For example, enter

```
% lmgrd -c license_file -l logfile -reuseaddr
```

### “Unsupported”

If the tool you are running attempts to check out a feature that is not in your license file, the license log file records an “Unsupported” message. This message is not an error message, but rather a message notifying you that your server does not support some features.

This message might also appear if your license administrator has updated the license file or license server after you started your Synopsys tool. If you receive an “Unsupported” message, but you are sure that the feature you are trying to check out is supported, restart the tool you are running.

---

## Filtering Information From the Server Log File

The SCL installation directory contains a tool named `watchlog.c` that filters the contents of the license server log file for certain types of messages. The `watchlog.c` file contains the source code and is part of the SCL installation (`scl_root/example/watchlog.c`).

You can use `watchlog.c` to monitor the FLEXnet `lmgrd` output log for specific events. When an event is found, you can run a script or program to take a specific action.

For example, you can monitor the log file for “DENIED,” then run a script that e-mails the license administrator with information about the denial.

## Building and Running `watchlog.c`

Because the tool is contained in one file, the build is straight-forward:

```
% cc -o watchlog watchlog.c
```

Run the tool from the piped output of `lmgrd` rather than specifying a log file for `lmgrd` (the `-l` option to `lmgrd` is not used):

```
% lmgrd -c synopsis.lic | watchlog watchlog.conf -o lmgrd.log &
```

Note that the command must be run in the background even though `lmgrd` normally backgrounds itself. This is because `watchlog` does not automatically run in the background.

## SETTING UP `watchlog.conf`

The configuration file for `watchlog` (which can be named anything you like as long as you use the same name as when you run `watchlog`) is a tab-delimited file with the pound sign (`#`) as the first character denoting a comment line. The first column is the regular expression you wish to look for in the log file. The second column is the action to take when that expression is matched. There are three actions that can be taken: drop the line from the log, execute a program, or send an email.

To drop a line from the log, the action is just the single word “drop.” Anything else in the action column is assumed to be a program to run, as shown in [Example 9-7](#).

**Example 9-7 Dropping a Line from a Log**

```
#This is the site "watchlog" configuration file for server
#"foo". We're going to filter out "bad handshake" messages
#and notify a sys-admin if we see DENIED or WARNING messages.
#We are also going to alert specific users when we see a
#license expiry message.
#
#Format
#-----
#pattern <tab> Action <space> Arguments
#where pattern = strings separated by spaces
#
#Regular Expression Action
# -----
[bB]ad [hH]andshake drop
DENIED adminmail dave
WARNING adminmail john
expires mailto="user1@company.com, user2@company.com"
EXPIRATION WARNING mailto="user1@company.com, user2@company.com"
```

You can use the following email addresses:

[user1@company.com](mailto:user1@company.com)

[user2@company.com](mailto:user2@company.com)

You can insert multiple tabs between the two columns, allowing you to align the columns; however, you must have at least one tab between the regular expression and the action. Any spaces in the regular expression are considered to be part of the expression. In [Example 9-7](#) the “bad handshake” message is dropped from the final output log. When a DENIED line is shown, the “adminmail” program (binary or script) with the parameter “dave” is executed. The first word in the action column is the program name. All other words are the program parameters. When the program is executed, `watchlog` puts the line that triggered the action as the last parameter to the program call.

When a WARNING appears, “adminmail” with the parameter “john” is executed.

“mailto” is a new internal action that can be used to send an email alert based on matching patterns. In [Example 9-7](#), when either “expires” or “EXPIRATION WARNING” occurs, an alert is sent to user1 and user2. The tool accumulates all the expiration warnings and sends a consolidated email every 24 hours.

## What Happens When the License Server Goes Down

When the license server connection is lost, active licensed tools go through reconnection phases. Tools requiring no new licenses do not exit. However, if the tool requests a new license while the server is down, the license cannot be issued, and the existing tool issues an SEC-12 message for the current license.

## Verifying the Content and Integrity of the License Key File

Entry errors and corruption of data in a license key file could be the source of various problems both in starting up the licensing system and acquiring licenses. (See [“Checking the Integrity of the License File” on page 3-2.](#))

### Checking Requisite License Key File Content: SERVER and VENDOR Lines

It is good practice to visually check the file for typographical errors and incorrectly specified information that you might have introduced in modifying the file. Do this if you encounter problems in starting up the `lmgrd` daemon or if users have trouble checking out licenses for supported features, even if you checked the license key file when you first installed it.

Check the SERVER and VENDOR lines for typographical and informational errors. Ensure that the server host name and the port number are correct and that the `snpslmd` daemon path name and options file, if specified, are correct. Check the USE\_SERVER line for correct spelling of the keyword.

At a minimum, visually check these aspects of the license key file:

- The SERVER line. Make sure the SERVER line specifies the correct host name for the host ID. The host name is the first parameter; the host ID is the second one. Errors in this entry could cause startup failures. Ensure that the port number is correct.
- The VENDOR line. Make sure the VENDOR line correctly specifies the SCL daemon, `snpslmd`. If you modified this line to also specify a path to the daemon, verify that the path information is correct. If you specified a path to the options file, ensure that the `snpslmd` daemon itself can be found. Errors in this entry could cause startup failures.

### Checking the Host ID

The host ID for the machine hosting the license server is used in the license key encryption process. The host ID shown on the SERVER line of the license key file must be that of the license server machine.

The `lmhostid` utility displays output similar to the following message:

```
lmhostid - Copyright (c) 1989-2008 Acresto Software Inc.  
All Rights Reserved. The FLEXnet host ID of this machine is
```

"833d63f3"

## Using lmdiag and lmstat to Diagnose Problems When You Cannot Check Out a License

You can use the `lmdiag` and `lmstat` utilities to diagnose the source of the problem when a user is unable to check out a license. You can also use these utilities to gather information about licenses currently in use and who is using them.

### Using lmdiag

You can use the `lmdiag` utility to test whether a license can be checked out for a specific feature when a user is denied the license. The utility prints out information about the feature, reporting whether the checkout failed or succeeded. If the license checkout fails, the reason for the failure is reported. If the server is down, the error message will report that this is the cause.

Here is the syntax for the `lmdiag` utility:

```
lmdiag [-c license_file] [-n] [feature]
```

Option	Description
<code>-c <i>license_file</i></code>	This is the path to the file containing the feature to be diagnosed.
<code>-n</code>	Executes the utility non-interactively. In this mode, <code>lmdiag</code> does not prompt you for input. (In this mode, extended connection diagnostics are not available.)
<code><i>feature</i></code>	Specifies the feature to be diagnosed. If no feature is specified, all features in the file are diagnosed.

The `lmdiag` utility first prints information about the license and then attempts to check out each license. If the checkout succeeds, the `lmdiag` utility indicates this. If the checkout fails, the `lmdiag` utility displays the reason for the failure. If the checkout fails because the `lmdiag` utility cannot connect to the license server, you should run "extended connection diagnostics." For complete information, see the Flexera *FLEXnet End Users Guide*.

### Using lmstat

You can use the `lmstat` utility to monitor the status of all network licensing activities, including all licenses in use and all users of licenses for specific features.

Here is the syntax for the `lmstat` utility:

```
lmstat [-a] [-A] [-c license_file] [-f feature_name]
[-i feature] [-s server] [-S vendor]
```

Option	Description
<code>-a</code>	Displays all information.
<code>-A</code>	Lists all active licenses.
<code>-c <i>license_file</i></code>	Specifies the license file to be checked.
<code>-f <i>feature_name</i></code>	Lists users of the specified feature.
<code>-i <i>feature</i></code>	Displays information about the named feature. If no feature is specified, displays information about all features.
<code>-s <i>server</i></code>	Displays status of all license files listed in <code>\$VENDOR_LICENSE_FILE</code> or <code>\$LM_LICENSE_FILE</code> . If no server is specified, displays information about all servers.
<code>-S <i>vendor</i></code>	Lists all users of the specified vendor's features.

## Getting Help

If you encounter problems that you cannot diagnose yourself, you can seek help by contacting Synopsys Customer Support. For information on how to contact customer support, see [“Customer Support” on page xiii](#).

When you call Synopsys customer support, have the following information at hand:

- The license key file or files referenced by the client
- Description of your licensing environment, for example, whether you are using three-server redundancy or multiple distributed license files
- The platform on which the license server is running
- Your site ID, as specified in the license key file
- The version number of the `snpslmd` daemon that you are running (See [“Determining Whether Your Tool Is Enabled for SCL” on page 9-14](#) for details on obtaining the version number.)
- The debug log file

- The output of `lmstat` utility

## Diagnosing Problems With FLEXnet

Some problems you encounter might originate in FLEXnet. To obtain diagnostic information about FLEXnet, set the `FLEXNET_DIAGNOSTICS` environment variable. When this variable is set, FLEXnet produces diagnostic information if a license checkout fails.

For information on how to set this variable and interpret diagnostic information, see the *FLEXnet End Users Guide*.

---

## Known Issues

This section contains known issues and workarounds for SCL 11.1.

---

### Licensing Checkout (Heartbeat) Errors

A heartbeat is a message and acknowledgment sequence between a Synopsys tool and a Synopsys license server. Heartbeats are initiated by the tool and inform the tool when a server goes offline. The interval between heartbeats is typically 120 seconds.

If the tool that sends the heartbeat message does not get a timely response from the license server, this lack of response is considered a heartbeat failure. Multiple heartbeat failures can cause licensing checkout failures. Eventually the tool might go into a suspended or sleep mode, or terminate abnormally.

Note:

The `TIMEOUT` and `TIMEOUTALL` features in the options file are not supported because they can contribute to heartbeat failures.

### Minimizing Heartbeat Failures

To minimize heartbeat failures, it is suggested that you have a 2-Gbps Ethernet network connection and an AMD or Intel x86\_64 hardware running the latest version of SCL software. This server should be configured as follows:

- Robust license server: AMD or Intel x86\_64 hardware running Red Hat Enterprise Linux version 4 or 5.
- 4 GB of memory.
- Single (not triple redundant) servers.

Redundant servers are not recommended because they are not robust in recovering from failures. Instead, use multiple single servers to achieve redundancy.

**Note:**

Keep in mind that the license server does not rely on heartbeats to check in licenses. Unless a tool requests that a license be checked back in, the only time a server checks in a license is if the TCP connection between the client (tool) and the server is closed. This can happen if the Synopsys tool terminates or if the network connection between a client and the server is lost.

---

## Tools Based on Legacy Daemons Fail to Start

Under certain conditions, the SCL11.x license server will not start properly and the license server serves keys only for the `snpslmd` daemon. This is a known SCL bug, which is being investigated.

Assuming that your setup is fine and you have the required licenses for the tools you are running, using the following methodology will resolve this problem.

1. Obtain your latest license file from Smartkeys. Many Synopsys tools will not run unless you have the latest licenses.
2. Make sure the FLEXnet version is at least 11.6.1. You can check the FLEXnet version by looking at the debug log file. If you don't have the correct FLEXnet version, download the latest version of SCL from the Release Library (see ["Registering for SolvNet and Downloading SCL" on page 4-2](#)).

3. Stop the license server by using `lmdown`:

```
% lmdown -c /path/to/synopsys.lic
```

4. Make sure that `snpslmd` is stopped (check by using `ps -ef | grep snpslmd`). If not, use the `kill` command to stop `snpslmd`.

5. Remove any Synopsys lock files in `/var/tmp`:

```
locksnpplmd lockCADABRA lockEPIC lockISE-TCADd
lockTE_CATS lockadalmd lockanagram lockavantd
lockchrysalisd lockeverest lockhsd lockinnologd
locksaber_dmn lockslatlockssilmd locksynopsysd
locktmald lockvcsd lockla_dmon lockleda lockmetasoftd
locknassd locknumeritchd lockpdlld locksandwork locksigmacd
locksynplctyd locksnpsoEM1
locksnpsoEM2 locksnpsoEM3
```

6. Log in as the license administrator and unset any Synopsys licensing variables. For example (in C-Shell), enter

```
% unsetenv AVANTD_LICENSE_FILE
% unsetenv LM_LICENSE_FILE
% unsetenv NASSD_LICENSE_FILE
% unsetenv SANDWORK_LICENSE_FILE
```

```
% unsetenv SNPSLMD_LICENSE_FILE
% unsetenv SYNPLCTYD_LICENSE_FILE
% unsetenv TMALD_LICENSE_FILE
```

Note:

If you use a script to start SCL, modify the script to unset these variables.

- Remove any `.flexlmrc` directory in your `$HOME` directory. Enter

```
rm -f $HOME/.flexlmrc
```

- Restart the license server.
- Have the tool users set the appropriate licensing environment variable. Depending on the tool and tool version, this is usually `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` (if unsure, set both variables). For example,

```
setenv SNPSLMD_LICENSE_FILE 27000@my_server
```

For a complete list of Synopsys legacy daemons, see [Table 1-2 on page 1-5](#).

---

## Legacy Applications Issue With License Pooling of Multiple Key Files

License pooling is the ability built into most Synopsys tools that enables them to use multiple license key files simultaneously. A tool that supports license pooling can check out one license from `server1` and a second license from `server2`.

However, if in a single tool session you are using a legacy bridge tool that includes both `snpslmd` code as well as `ascode` for a legacy daemon, you might not be able to check out a license from both `server1` and `server2`.

To resolve this issue, set the `SNPSLMD_DAEMON` environment variable to `OFF` before invoking the legacy tool.

```
% setenv SNPSLMD_DAEMON OFF
```

### Important:

This variable is not needed for the z2007.09 release or later. Also, do not set this variable for Astro in Galaxy Mode, or for Milkyway, IC Compiler, or Physical Compiler.

To determine if a tool has SCL code, use the `whatscl` utility included with SCL. For example,

```
% cd /synopsys/hspice_2009.03/linux
% whatscl hspice
Synopsys Corporate Licensing (SCL) Release: version SCL_11.1,
Build 1; Label: SCL_11.1; Built on Sep 22 2009 at 23:41:36
```

To determine if a tool has legacy code, use the UNIX `strings` command. For example,

```
% strings hspice | grep avantd  
  
avantd  
avantd  
avantd  
...
```

In this case, the tool is a bridge tool that includes both SCL and `avantd` code. For more information on license pooling, see [“License Pooling Functionality” on page 2-2](#).

---

## SCL License Server Out-of-File Descriptors on Linux Operating Systems

The following error message indicates that the server has run out of file descriptors:

```
(lmgrd) Can't open /usr/tmp/.flexlm/lmgrdl.3343, errno: 24
```

If you get such messages, increase the file descriptor on the server. Linux has a default file descriptor limit of 1024 per user. However, a system administrator can increase the number of allowed open descriptors up to a value of 64k. For details on how to do this, see

[http://kbase.redhat.com/faq/FAQ\\_80\\_1540.shtm](http://kbase.redhat.com/faq/FAQ_80_1540.shtm)

In general, Synopsys recommends a file descriptor setting of 8x the number of licenses. Therefore, if you have a total quantity of 1,000 licenses, the descriptor setting should be 8192.

---

## lmgrd Error Message: Failed to open the TCP port number in the license

If you get an “(lmgrd) Failed to open the TCP port number in the license” error message, stop all SCL processes and restart the server.

On Windows systems,

1. Stop any SCL processes such as `lmgrd` and `snpslmd` (for `lmgrd`, use the `kill` command only; do not use `kill -9`).
2. Restart `lmgrd` by using `lmttools`.

If this does not help, change the TCP port specified in the `SERVER` line of the license file (see [“Modifying SERVER Line Data Items” on page 5-8](#)), or contact your local Support Center.

On UNIX or Linux systems,

1. Stop any SCL processes such as `lmgrd` and `snpslmd`. (Use the `kill` command only; do not use `kill -9`.)

2. Restart `lmgrd` with the `-reuseaddr` switch:

```
% lmgrd -c synopsys.lic -l debug.log -reuseaddr
```

If this process fails, continue with step 3:

3. Make sure the `/etc/hosts` file has a `127.0.0.1 localhost` entry. Enter

```
% cat /etc/hosts
```

```
127.0.0.1 localhost
```

4. Edit the `/etc/nsswitch.conf` file.

Locate the `hosts` and `networks` lines and make sure the first entry after the colon refers to `files`. For example,

```
hosts: files [NOTFOUND=continue] dns
networks: files [NOTFOUND=continue] nis
```

5. Save any changes and repeat steps 1 and 2.

If this does not help, change the TCP port specified in the `SERVER` line of the license file (see [“Modifying SERVER Line Data Items” on page 5-8](#)) or contact your local Support Center.

---

## SCL Crashes With Errors in the Debug Log File

If Synopsys Common Licensing (SCL) 11.1 fails or is unable to serve licenses, you will generally see errors in the debug log file. The following errors are common:

### lmgrd Errors

```
8:24:52 (lmgrd) Can't open /usr/tmp/.flexlm/lmgrdl.1655, errno: 24
```

```
20:47:11 (lmgrd) Error 11 sending message to client
```

```
16:15:33 (lmgrd) Vendor daemon died with status xx [where xx is a number such as 37, 39, or 50]
```

### snpslmd Errors

```
16:15:33 (snpslmd) Vendor daemon can't talk to lmgrd (Cannot read data from license server system. (-16,287))
```

```
4:04:56 (snpslmd) Error 0 sending message to client
```

20:52:02 (snpslmd) Lost connection to lmgrd, heartbeat timeout expired, exiting.

8:29:46 (snpslmd) Lost connection to lmgrd, exiting.

In general, the license server will shut down following these messages. This is indicated by SHUTDOWN messages in the debug log file. The license server might attempt to restart, but restart attempts will often fail.

## Causes

If the socket connection between `lmgrd` and `snpslmd` is broken, or if the `lmgrd` (or `snpslmd`) process does not respond to heartbeat messages because it has died or is busy, one or more of these error messages will be displayed in the log file, and the server will shut down.

Although the errors indicate a lack of system resources, there is no single cause.

Things to monitor:

- High CPU utilization on the system
- Lack of file descriptors
- Lack of available memory
- A slow or erratic network connection
- Dropped TCP packets

The problem might be intermittent, depending on the load on the license server. If this problem occurs on an ongoing basis, the general resolution is to rehost the licenses to a more powerful license server with a better network connection. For details, see [“Hardware, Operating System, and Other Requirements” on page 2-3](#).

## Resolution

### 1. Check your SCL version.

```
1. % lmver lmgrd      #Should be 11.6.1
   % lmver snpslmd   #Should be 11.6.1.6
   % scl_root/platform/bin/whatscl snpslmd
   #Should be 11.1
```

### 2. Make sure you are using a supported operating system and operating system version. For a list of supported operating systems, see [Table 1-1 on page 1-3](#) or the *Synopsys Common Licensing Release Notes* in SolvNet.

### 3. Monitor your license server for low resources:

- You can use `top` or `ntop` to monitor for CPU and memory usage. If CPU usage goes over 95 percent, this is a cause for concern.

- Monitor for dropped TCP packets with this command.

```
netstat -s -P tcp | grep tcpListenDrop
```

- On Solaris, you can monitor for low resources with the SE toolkit, an interactive tool. Download this free software at

```
ftp://ftp.sunfreeware.com/pub/freeware/SOURCES/RICHPse.gz
```

#### Usage

```
% cd $INSTALL_DIR/RICHPse/examples/
% ../bin/se tcp_monitor.se &
% ../bin/se zoom.se &
```

This code sequence brings up two windows. You can monitor the TCP activities and the system resources with this tool. Make sure that all the system and TCP status data are either in green or white. If any items are displayed in red or black, you have a system resource issue that must be resolved.

#### 4. Contact Support.

If resource usage seems OK, open a call to your local Support Center and send the following information:

- A copy of the debug log file
- The results of the following UNIX commands:

```
% pfiles process_id #Process id of lmgrd process
% pfiles process_id #Process id of snpslmd process
% uname -a
% netstat -i
% netstat -s
% lmver lmgrd
% lmver snpslmd
% scl_root/<platform>/bin/whatscl snpslmd
```

# A

## Starting SCL on Windows Platforms With LMTOOLS

---

This appendix is intended to help you configure, start, and troubleshoot a FLEXnet license server on Windows platforms using LMTOOLS.

This chapter includes the following sections:

- [General Information and Installation](#)
- [SCL Components](#)

---

## General Information and Installation

This section contains the following topics:

- [SCL Components](#)
- [Starting SCL Automatically With LMTOOLS](#)

---

## SCL Components

The following components make up SCL licensing on Windows platforms:

- `lmgrd`, `snpslmd`, LMTOOLS, and other FLEXnet binary files distributed with SCL
- A parallel port or USB dongle (although the Ethernet ID can also be used)
- The dongle software driver
- The license key file obtained from Synopsys

---

## Starting SCL Automatically With LMTOOLS

Follow these steps to install and run SCL with LMTOOLS:

1. Install SCL 11.1 or later using the default path. The default installation folder for the binary files and tools is

```
C:\synopsys\SCL_11.1\windows\bin
```

2. Edit the license file. Change only the SERVER and VENDOR lines

Assuming these two lines look like this:

```
SERVER hostname1 FLEXID=9-07B4ABE9 27000
VENDOR snpslmd /path/to/snpslmd
```

- a. Change the SERVER line to include the PC's host name, and customize the port number if desired. For example,

```
SERVER my_server FLEXID=9-07B4ABE9 27010
```

- b. Change the VENDOR line to reflect the path to the `snpslmd` vendor daemon. For example,

```
VENDOR snpslmd C:\synopsys\SCL_11.1\windows\bin\snpslmd.exe
```

Save the file as

C:\synopsys\SCL\_11.1\admin\license\synopsys.lic

Installing the software creates Start menu items under Start > Programs > Synopsys > SCL\_11.1.

3. For license files that specify a dongle host ID (also called a FLEXID), make sure the dongle is properly connected to your system. Check to see if the dongle is recognized by invoking LMTOOLS from the start menu and clicking the System Settings tab. The dongle ID is displayed in the large FLEXID box on the lower left.

If the dongle is not recognized, install the dongle driver included with SCL. For detailed information about using dongles, see [“Ordering FLEXnet Dongles and Installing Dongle Drivers” on page A-4.](#)”

4. Configure `lmgrd` to run as a service in Windows using the following steps:
  - a. Invoke LMTOOLS from the Start Menu (Start > Programs > Synopsys > SCL\_11.1 > LMTOOLS).
  - b. On the Service/License file page, select “Configuration using Services.”
  - c. Click the Config Services tab.
  - d. Enter a Service Name (for example, Synopsys) and press the Tab key. The following three fields should be empty.
  - e. Next to “Path to the `lmgrd.exe` file,” click Browse and browse to the path of `lmgrd.exe` inside the SCL installation tree.
  - f. Next to “Path to the license file,” click Browse and browse to the path of `synopsys.lic`
  - g. Next to “Path to the debug log file,” enter this path:  
C:\synopsys\SCL\_11.1\admin\logs\debug.log
  - h. At the bottom of the Config Services page, select “Use Services,” then select “Start Server at Power Up.”
  - i. Click Save Service, then click Yes to confirm.
5. Click the Start/Stop/Reread tab. Make sure your service name is highlighted. Click Start Server.
6. Make sure the server has started correctly by viewing the debug log file. (Click the Config Services tab, then click View Log.) Verify that there are no `SSS` or other errors.
7. (Optional) From within LMTOOLS, go to the Server Status tab and click Perform Status Enquiry. A list of available licenses should appear.
8. Set your license variable to the correct `port@host` value (`27010@my_server` in the step 2 example):

- a. In the Control Panel, click System > Advanced > Environment Variables.
  - b. Under System Variables, click New.
  - c. In the New System Variable box, next to Variable name, enter  
SNPSLMD\_LICENSE\_FILE or LM\_LICENSE\_FILE.
  - d. Next to “Variable value,” enter the TCP port, followed by the @ symbol and the host name specified in the license key file. For more information about licensing variables, see [“Describing the License Environment Variables” on page 6-4](#).
9. Invoke your application. If you encounter any errors, see [“Troubleshooting Tool Startup Problems” on page A-10](#).

---

## Ordering FLEXnet Dongles and Installing Dongle Drivers

If you are running Synopsys tools on a Windows platform and have node-locked licenses, you might be required to use a dongle.

A dongle-based license can be distinguished from a regular license based on the Ethernet or MAC address for Windows platforms by the FLEXid prefix it contains. For example,

```
FLEXID=9-07B4ABE9
```

Dongle licenses can be normal networked licenses usable by anyone on the network, or they can be node-locked licenses that can be run only on the system with the MAC address or dongle ID specified. Networked licenses have the FLEXid prefix and the dongle ID specified on the SERVER line; node-locked licenses have a special `HOSTID=` field in the individual INCREMENT lines.

To be compatible with the USB dongle, the Synopsys tool must be built with FLEXnet 7.2g or later. You can check the FLEXlm or FLEXnet version of the application by using the `lmver` utility included with SCL.

This section includes the following topics:

- [Ordering a FLEXnet Dongle for Synopsys Tools](#)
- [Installing Dongle Drivers on Windows Systems](#)

## Ordering a FLEXnet Dongle for Synopsys Tools

Customers that use Synplicity products should contact their Synopsys Account Manager for dongles. Synopsys will ship the dongles to them. As of March, 2010, all new dongles issued for Synplicity products are of the FLEXID=9- type, which supports both server-based and serverless licenses.

Customers using non-Synplicity products should order a new dongle from Flexera Software (formerly Acresto Software). Their website is <http://www.flexerasoftware.com>

Before you order a dongle, make sure that your Synopsys tool supports a FLEXnet dongle. Synopsys supports dongles only for certain tools, running on a supported 32-bit or 64-bit Microsoft Windows OS. To determine whether you can obtain dongle-based licenses for your Synopsys tools, contact your sales representative.

To obtain a dongle for your Synopsys product, you must order it from Flexera Software by following these steps:

1. Send an e-mail to [flexid@flexerasoftware.com](mailto:flexid@flexerasoftware.com) or call them at 44 870 873 6300 or 44 1928 706 6346.

2. Request a quote for a dongle.

Important:

Be sure to specify that you are a Synopsys customer; otherwise, Flexera Software will not process your order.

3. Place the order by following the procedure specified by Flexera Software.
4. When you receive the dongle, send the dongle host ID to your sales representative. This host ID (needed to create your license key file) is printed on the dongle. If this order is related to the rehost of an existing license key file, you must fill out a rehost form.

## Installing Dongle Drivers on Windows Systems

For the dongle ID to be seen by the `lmgrd` command, you must install the dongle software driver. The drivers supplied with the dongle from Flexera Software and those supplied with Synopsys software support the following dongle types:

Dongle Type	Description
Type 7	teal parallel port dongle
Type 8	black parallel port dongle
Type 9	green USB dongle
Sentinel dongle (SKEY=)	either grey or white

SCL is not guaranteed to work with older versions of dongle drivers.

For best results, do the following:

1. Uninstall any old drivers.
2. In the Control Panel, open “Add or Remove Programs.” Remove any old drivers, such as FLEXID Driver, Macrovision Driver, Globetrotter FLEXid Drivers, or Sentinel System Drivers.
3. Run the `FLEXidCleanupUtility` cleanup with SCL.
4. Install the new drivers with the provided `FLEXidInstaller` or `IDInstaller` executable file.
5. With the dongle firmly inserted into the parallel port or USB port, shutdown and restart the system.
6. Open LMTOOLS and look for the dongle ID on the System Settings page. Make sure that the dongle ID is correctly specified in the FLEXID box in the lower left of the window.  
If the dongle ID is not correctly specified, see [“Troubleshooting Dongle Problems”](#) next.

---

## Node-Locked Uncounted and Counted Licenses

A node-locked license has a hostid on any INCREMENT line that is node-locked to a particular host. The two types of node-locked licenses are uncounted and counted.

### Uncounted Node-Locked License Keys

You do not need a license server in order to have an uncounted node-locked license key. You can simply retrieve your new license key from SmartKeys, and use it. The following example shows a serverless, node-locked license:

```
INCREMENT synplifydsp snpslmd 2010.12 31-dec-2010 uncounted \
  7DFB833A7EF6AB0703DD VENDOR_STRING=fpga,n1 \
  HOSTID= FLEXID=9-07B4ABE9 \
  ISSUED=01-jun-2009 ck=159 SN=RK:4842-0:1067383:810881 \
  START=01-Jun-2009
```

The license file is node-locked to a USB dongle (FLEXid = 9-07B4ABE9). Make sure that you install the dongle driver before attaching the dongle and invoking the tool.

### Counted node-locked license keys

You must have a license server in order to have a counted node-locked license key. The following example shows a counted node-locked license.

```
INCREMENT synplifydsp snpslmd 2010.12 31-dec-2010 2 \
  VENDOR_STRING=fpga HOSTID= FLEXID=9-07B4ABE9 \
  ISSUED=01-jun-2009 ck=159 SN=RK:4842-0:1067383:810881 \
```

```
START=01-Jun-2009 AUTH={ snpslmd=(LK=ADFC38B781C96F3C597) }
```

The license file is node-locked to a USB dongle (FLEXid = 9-07B4ABE9). Make sure that you install the dongle driver before attaching the dongle and invoking the tool.

---

## Troubleshooting Dongle Problems

This section outlines the steps to follow in using a dongle and provides tips for dealing with problems that might arise. For the dongle ID to be seen by FLEXnet, a FLEXID software driver must be installed. The software driver is configured on Windows to start as a device driver.

If a dongle is not recognized, any of the following causes might be responsible:

- The wrong version of LMTOOLS has been invoked
- No dongle driver is installed
- The existing driver is obsolete
- A conflict with an old driver or another device exists
- An operating system problem exists or the dongle is defective

To check for these problems, do the following:

1. Start only the LMTOOLS utility provided with SCL 11.1.
2. Click the System Setting tab and make sure the correct dongle ID shows in the FLEXID field. If the correct ID does not show, try the following:
  - a. Make sure the parallel port dongle is attached directly to the parallel port, not to another device.
  - b. Make sure the USB dongle is attached directly to the system, not to a USB hub device.
  - c. Remove and reinsert the dongle.
  - d. Uninstall any old drivers by using the Add or Remove Programs Control Panel application. Old drivers have names such as Globetrotter FLEXID Driver, Macrovision FLEXID Driver, and Sentinel System Driver.
  - e. Restart the system.
  - f. Run the FLEXIDCleanupUtility cleanup utility provided with SCL.
  - g. Run FLEXIDInstaller or IDInstaller (included with SCL) to install the latest drivers. Make sure to specify the correct dongle prefixes.

- h. Restart your machine and repeat steps 1 and 2. If the dongle driver is still not recognized, try these steps on another machine or contact Synopsys Support.

---

## Troubleshooting SCL Startup Problems

The following topics are included:

- [SCL Service fails to Start Automatically on Windows Platforms](#)
- [Errors in the Debug Log File](#)

### SCL Service fails to Start Automatically on Windows Platforms

In some cases, the SCL server does not start properly when the system is restarted, even though LMTOOLS has been configured to start the SCL service automatically.

The usual cause is that the system tries to start SCL before the dongle driver has been loaded. In such cases, SCL will not start because it cannot find a valid host ID. The solution is to delay the startup of SCL.

To enable service delay for a particular service,

1. Start the Registry Editor:
  - a. Click Start > Run and enter `Regedit`.
  - b. Locate the registry entry for the Synopsys license service:  
`HKEY_LOCAL_MACHINE\SOFTWARE\FLEXIm License  
  \Manager\service_name`  
where `service_name` is the name of the license server service you configured in LMTOOLS.
2. Click Edit > New > String Value.
  - a. Type `serviceDelay` and press Enter.
  - b. Right-click the `serviceDelay` icon you created and click Modify.
  - c. Enter a value of 3 to delay SCL startup by three seconds, then click OK (the value can be 1 through 20 seconds).

You should now see the following information in the right pane of the Registry Editor:

Name	Type	Data
serviceDelay	REG_SZ	3

3. Exit the Registry Editor.

## Errors in the Debug Log File

The debug log file should be checked every time the server is started or reread. (The log file is a text file that is in the location specified on the Config Services page of LMTOOLS.) The following discussion describes common debug log file errors and their solutions.

**Problem:** The debug.log file contains a “Failed to open the TCP port number” error message after starting the license server.

**Solution:** In LMTOOLS, stop the license server. In Task manager, stop all instances of `lmgrd` and `snpslmd`. Restart the Synopsys SCL service. If this doesn’t resolve the problem, change the TCP port specified on the SERVER line of the license key file and repeat the enable service delay steps.

If following these steps still fails to resolve the issue, you might have a personal firewall running. See [“Troubleshooting Firewall Problems” on page A-10](#).

**Problem:** `SSS` errors in debug logfile.

**Solution:** Download the latest license key file from Smartkeys and run `sssverify`.

**Problem:** “Error - lmgrd refused vendor name list. This daemon will only serve licenses for the primary vendor” appears in the `lmgrd` log file and licenses cannot be checked out.

**Solution:** This issue is most often caused by running an earlier version of `snpslmd` and trying to use a later version of SCL.

**Problem:** “Future file format” error message in `lmgrd` log file when starting the server.

**Solution:** Most likely you have used an older version of `lmgrd` with the current version of `snpslmd`.

Check the debug log file and make sure that the FLEXnet version for `lmgrd` and `snpslmd` is 11.6.1 or later. Download the latest version of SCL and use the binary files from this version.

---

## Troubleshooting Tool Startup Problems

In this section, the following topics are covered:

- [General Troubleshooting](#)
- [Troubleshooting Firewall Problems](#)
- [The FLEXnet License Finder Dialog Box](#)

### General Troubleshooting

If the tool will not start, verify that `SNPSLMD_LICENSE_FILE` or `LM_LICENSE_FILE` has been set to the correct *port@host* value. For troubleshooting purposes, consider setting both variables.

Make sure the license server is running and that the feature is available (in LMTOOLS, click the Server Status tab, then click Perform Status Enquiry).

If the feature is available, make sure that the version is correct. For example, an `hspice` or `hspicewin 2009.12` feature is required to enable HSPICE D-2009.12 or earlier unless you have an on-support key. If the version is not correct, retrieve the latest license key file from SmartKeys at <https://solvnet.synopsys.com/SmartKeys>

All tool requests should be logged with an appropriate checkout message.

If the request cannot be granted, you should see an error. Check the debug log file for `SSS` errors, `DENIED` errors, or `UNSUPPORTED` messages.

Note:

An `UNSUPPORTED` message is not necessarily an error. This message means that the tool requested a license that is not available in the license key file. Often, the tool will then look for an alternate license.

### Troubleshooting Firewall Problems

Firewalls and internet security programs (for example, Norton Internet Security) can block TCP ports and keep `.exe` files from running.

- If you have a personal firewall installed, make sure that `lmgrd.exe` and `snpslmd.exe` have TCP access privileges.
- If you have a network firewall, modify the license key file to assign the `snpslmd` daemon a port at the end of the `VENDOR` line (this is normally determined randomly.) Then open up both the `lmgrd` and `snpslmd` ports. For example,

```
SERVER my_server 0003DC78E712 27010
VENDOR snpslmd C:\synopsys\SCL_11.1\admin\license\synopsys.lic
port=27011
```

## The FLEXnet License Finder Dialog Box

If no valid variable or feature (key) is available, or the specified server cannot be contacted, certain Windows tools display the FLEXnet License Finder dialog box and request that you specify a license file or server name.

Assuming the requested feature is available, you might have to enter the *port@host* name multiple times until the license request is satisfied.

To resolve this problem, follow these steps:

1. Make sure the license server is running and available.
2. From within LMTOOLS, click the Server Status tab, then click Perform Status Enquiry. A list of available licenses should appear. If none do, click the Config Services tab, then click View Log for error information.
3. If the license is available, try setting `LM_LICENSE_FILE` rather than `SNPSLMD_LICENSE_FILE` (or set both values). If this fails, modify the license key file and change the `lmgrd` port (specified at the end of the `SERVER` line) to something outside the range of 27000-27009, such as 28000. Exit the tool and restart it.
4. If the previous step does not help, modify the license key file to assign the `snpslmd` daemon port to a value outside the range of 27000-27009. For example, add `port=28001` to the end of the `VENDOR` line. Stop and restart the server.

Open the Control Panel and select System > Environment variables. Set `LM_LICENSE_FILE` to the `snpslmd` port (for example, 28001) instead of to the `lmgrd` port. Exit the tool and restart it.



# B

## SCL Command-Line Interface

---

This appendix describes the most commonly used SCL shell (sclsh) commands to test and validate the license server. This appendix includes the following sections:

- [Getting Help on Commands](#)
- [Validating a License Key on the License Server](#)
- [Testing the License Server for Performance](#)

---

## Getting Help on Commands

SCL provides two levels of help information: a list of commands and command usage help.

---

### Listing Commands

The `help` command lists the names of all `sclsh` commands. To display a list of all commands, enter `help` at the `sclsh` prompt.

```
% (sclsh) help
```

The following list appears:

<code>attr</code>	<code>auth_data</code>	<code>ci</code>	<code>clppath</code>	<code>co</code>
<code>disconn</code>	<code>dup</code>	<code>error</code>	<code>exit</code>	<code>expire</code>
<code>feat_count</code>	<code>free</code>	<code>help</code>	<code>int</code>	<code>incr</code>
<code>list</code>	<code>lmstatus</code>	<code>mci</code>	<code>mco</code>	<code>mcoci</code>
<code>manymcoci</code>	<code>path</code>	<code>queue</code>	<code>quit</code>	<code>set</code>
<code>setenv</code>	<code>sleep</code>	<code>tz</code>	<code>unset</code>	<code>usage</code>
<code>userlist</code>	<code>version</code>	<code>?</code>	<code>child</code>	

---

### Getting Command Usage Help

To get help about a specific `sclsh` command, enter the command name and the `-help` option.

### Syntax

```
command_name -help
```

### Example

To get help about the `co` command, enter

```
sclsh> co -help
```

The command usage `help` displays the command's options and arguments.

---

## Abbreviating Commands and Options

You can abbreviate `sclsh` command names and options to the shortest unambiguous (unique) string. For example, you can abbreviate the `release` command to `rel`. You can shorten an option name if the abbreviation is unique to the command. For example, to abbreviate the `coverage` command to `cov`, enter

```
% sclsh> set coverage cov
% sclsh> cov
```

Command abbreviation is meant as an interactive convenience. Do not use command or option abbreviations in script files because script files are susceptible to command changes in subsequent versions of the application. Such changes can cause abbreviations to become ambiguous.

---

## Arguments

Many `sclsh` commands have required or optional arguments. These arguments allow you to further define, limit, or expand the scope of the command's operation.

- Arguments that do not begin with a hyphen (-) are positional arguments. They must be entered in a specific order relative to each other.
- Arguments that begin with a hyphen are nonpositional arguments. They can be entered in any order and can be intermingled with positional arguments. The names of nonpositional arguments can be abbreviated to the minimum number of characters necessary to distinguish the nonpositional arguments from the other arguments.
- Arguments are enclosed in square brackets ([]).

If you omit a required argument, an error message and a usage statement appear.

## Comment Character

The `sclsh` command language uses the pound sign (#) to start a comment. The comment can start anywhere on a line. It ends with the end of the line.

---

## Validating a License Key on the License Server

Use the following command sequence to check out a particular version of a key from the license server:

```
% sclsh
sclsh> init #Initialize the licensing module.
sclsh> co key_name [count] [version] [qflag] #Check out a
```

```

    license from the license server.
sclsh> free #Free the licensing resources.
sclsh> ci key_name #Return the license back to the license
server.
sclsh> quit #Exit the application.

```

Use the `co` command to check out one or more keys of the specified version.

### Syntax

```
co key_name [count] [version] [qflag]
```

These are the options:

*count*

The number of licenses to check out (must be > 0).

*version*

The version of the key in year, month format (YYYY.MM).

*qflag*

Check out option flag `q|w|l|n` where the flags are equivalent to the following options:

`q` — `LM_CO_QUEUE`, queue for a license if all the keys are consumed.

`w` — `LM_CO_WAIT`, queue for a license if all the keys are consumed.

`l, t` — `LM_CO_LOCALTEST`, verify whether a valid key is present, but do not check out.

`n` — `LM_CO_NOWAIT`, do not queue for a license if all the keys are consumed.

---

## Testing the License Server for Performance

Two types of commands are available to test the license server performance.

- [Commands to Validate the Socket Connection Limit](#)
- [Commands to Stress Test the License Server With Multiple License Requests](#)

Note:

Do not use these commands on a production license server.

---

### Commands to Validate the Socket Connection Limit

Use the multiple check-out (`mco`) and multiple check-in (`mci`) commands to establish or create multiple socket connections to the license server. Each socket connection will check out a single license from the license server and will keep the license until the `mci` command is invoked.

### mco Command

Use the `mco` command to test the number of socket connections your license server can accept. This command does not stress test the license server. Each license is checked out through a separate socket connection. The licenses remain checked out from the server with the help of each socket connection until you release them by invoking `mci`.

The syntax is

```
mco key_name [count] [version] [qflag]
```

### mci Command

Check in the license that was checked out by the `mco` command.

You can also use the secondary daemon prefix to check out the license from the combined vendor daemon secondary daemons.

The syntax is

```
[secondary_daemon] mco key_name [count] [version] [qflag]
[secondary_daemon] mci
```

Here is a sample output of the `mco` and `mci` commands:

```
% sclsh> mco Design-Compiler 5 2009.12

Check-out Design-Compiler key checking out Design-Compiler
(v2005.12) license #1...done checking out Design-Compiler
(v2005.12) license #2...done checking out Design-Compiler
(v2005.12) license #3...done checking out Design-Compiler
(v2005.12) license #4...done checking out Design-Compiler
(v2005.12) license #5...done

sclsh> mci Design-Compiler #Check in all the Design-Compiler
keys checking in ALL features...done
sclsh> quit #Quit the application.
```

## Commands to Stress Test the License Server With Multiple License Requests

Two commands are available to stress test the license server or bombard the license server with multiple requests: `mcoci` and `manymcoci`.

### mcoci Command

The `multiple check out and check in (mcoci)` command checks out and checks in a license key in a continuous loop with the help of a single-socket connection (in the case of `mco`, the license is checked out only once). You can specify that multiple socket connections be created so that check out and check in activities occur with each socket connection.

**Syntax**

```
[secondary-daemon] mcoci key_name [repetitions] [count]
[-delay seconds]
```

The options are the following:

**secondary-daemon**

Indicates the secondary daemon name to be used for check-out/check-in

**key\_name**

Indicates the key name to check-out or check-in.

**repetitions**

Indicates the number of times to execute the check-out/check-in loop.

**count**

Indicates the number of keys to be checked out via each socket connection.

**-delay seconds**

Indicates the number of seconds to wait between check out and check in. The `mcoci` command creates multiple socket connections. The license key is checked out and checked in on each connection, in a `continue` loop. This happens as part of a single process. However, in a production environment where you have many computers in a farm, you will have many processes interacting with the license server. To simulate this environment, you must run multiple sessions of the `sclsh` utility with the `mcoci` command. To help achieve this goal, you can invoke the `manymcoci` command.

**manymcoci Command**

The many multiple check out and check in (`manymcoci`) command creates multiple `sclsh` processes. Each process creates multiple socket connections to the license server, and with the help of each socket connection, check-out and check-in of the license key can be performed in a loop. This simulates a compute farm environment. Make sure that you have large quantities of license keys available to test this scenario.

When you invoke the `manymcoci` command, a command prompt is provided that allows you to check the status of the processes invoked by the command (by invoking the `stat` command on the prompt). It also allows you to kill all the child processes and quit the application. After the `manymcoci` command completes its execution, it prints the status of all the child processes and the check-out and check-in status.

**Syntax**

```
[secondary-daemon] manymcoci feature [-quiet] [-delay seconds] [-children
integer]
[-childjobs integer] [-childloops integer]
```

The options are the following:

*secondary-daemon*

The vendor daemon to be used for check-out or check-in.

*key\_name*

Specifies the feature to check-out or check-in.

*quiet*

Disables the control prompt during the run (useful when using a `sclsh` input file).

*delay seconds*

The number of seconds to wait between each check-out and check-in.

*children integer*

The number of child processes to create. The value passed to the child process `mcoci` delay switch.

*childjobs integer*

The number of socket connections the child processes should create for each check out and check in loop. The value is passed to the child process `mcoci` job-count parameter.

*childloops integer*

The number of loops the child process should execute for the `check-out` or `check-in` command. The value is passed to the child process `mcoci` repetitions parameter.

When you are running `manymcoci`, the following commands are available at the command prompt:

*help*

Prints the available commands for the subprompt.

*stat*

Prints the current status of the child processes.

Here is an example of a `manymcoci` set of commands and output report:

```
% sclsh> manymcoci Design-Compiler -delay 2-children 5 -childjobs 5 \
-childloops 50
>>help #A new prompt is displayed: the commands supported are stat,
#help, and quit.
Enter one of the following commands: help, stat, quit
>>stat #Shows the status of all the child processes.
```

*Table B-1*

<b>ID</b>	<b>state</b>	<b>total</b>	<b>okays</b>	<b>fails</b>	<b>loop</b>	<b>error</b>	<b>stat</b>
1	running	5	5	0	1		

*Table B-1*

<b>ID</b>	<b>state</b>	<b>total</b>	<b>okays</b>	<b>fails</b>	<b>loop</b>	<b>error</b>	<b>stat</b>
2	running	5	5	0	1		
3	running	5	5	0	1		
4	running	5	5	0	1		
5	running	5	5	0	1		

When the output report is complete, the final status of all processes is printed to your screen before the main `sclsh` prompt reappears.

# C

## SCL License Key File Sort Utility

---

This appendix describes the Synopsys Key File sort (`sclsort`) utility. This appendix includes the following sections:

- [Features](#)
- [Usage](#)
- [Examples](#)

The Synopsys Key File sort (`sclsort`) utility is command-line based and can be used to reorder the Synopsys license key file that you retrieve from SmartKeys. This utility reorders the license keys in the license key file, based on several fields in the INCREMENT line.

---

## Features

The `sclsort` utility has the following features:

- The `sclsort` utility writes the reordered license keys to a new license key file; it does not overwrite the existing license key file.
- All comment lines before the `SERVER` line are retained in the new license key file. (Note that comment lines are the ones beginning with `#`.)
- No changes are made to any of the individual `INCREMENT` lines.
- Any changes made by this tool to the license key file will not affect the output of other utilities, such as the `sssverify` utility and product-to-feature mapping.
- After a new license key file has been generated, you can run the `sssverify` utility in order to validate the license key file.

The `sclsort` utility can reorder the keys in a license key file, based on the contents of the following fields:

- Key name (`feat`)
- Expiration date (`expdate`)
- Start date (`startdate`)
- Version number (`version`)
- Issued date (`issuedate`)
- Number of keys (`numkeys`)

By default, the license key is sorted based on the license key name. The user has an option of specifying a max of two fields for sorting. If there are any expired keys in the key file, they are moved to the end of the key file, irrespective of sorting order.

This utility can be used with both legacy and CVD-formatted key files as well as node-locked license key files and floating license key files.

If you have revenue and temporary keys in the same license key file, the revenue key files are sorted separately from the temporary key files. For temporary keys, the block of temporary key files with the associated `SSST` key is sorted separately. If you have multiple blocks of temporary keys, each with its own `SSST` key, each block of keys is sorted separately. Every `SSST` key block can be identified by its transaction ID.

**PACKAGE keys:** The `INCREMENT` line that corresponds to a `PACKAGE` key is sorted along with the other `INCREMENT` keys. The `PACKAGE` key can be found before the first `INCREMENT` line associated with the `PACKAGE`.

---

## Usage

The `sclsort` utility is located in the `scl_root/platform/bin/` directory, as shown in the following syntax:

```
% sclsort
[-h|-help]
-p sortfield [:a|:d]
[ -s sortfield [:a|:d]]
-i infile
[ -o outfile]
```

The `sclsort` utility has the following options:

- h|-help Prints the help message
- p Specifies the primary sort field with *sortfield*. If you do not use this option, the license key file is sorted based on key names. You can continue to sort each subsequent field in either ascending or descending order by specifying either - :a or :d, respectively. The default sort order is descending, except for when you use the key name.
- s Specifies the secondary sort field with *sortfield*. That is, once the file is sorted on the primary sort field, it is sorted again on this sort value. You can continue to sort each field in either ascending or descending order by specifying either - :a or :d, respectively. The default sort order is descending, except for when you use the key name. If you do not use the secondary sort field, the license key file is sorted only on the primary sort field.
- i Specifies the input license key file.
- o Specifies the output license key file. The default is stdout.

The `sclsort` utility supports the following sort fields:

- feat Specifies to sort by key name
- expdate Specifies to sort by expiration dates
- startdate Specifies to sort by start date

<code>issuedate</code>	Specifies to sort by issue date
<code>numkeys</code>	Specifies to sort by the number of keys
<code>version</code>	Specifies to sort by the version number

---

## Examples

The following subsections show various uses of the `sclsort` utility.

---

### Using a Feature Name in Descending Order

The following example uses the input file `in.lic`:

```
INCREMENT certify snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=altera,xilinx \
  ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \
  START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCBd \
  28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \
  OCD1 DDE0 C9CC 7D50 56D0") }

INCREMENT spice snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=184 \
  SN=TK:5096-0:871303:843082 START=05-mar-2007 \
  AUTH={ snpslmd=( LK=71C3F3F78009) \
  sandwork=( SIGN=E3C45AB6E84E) }

INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
  SN=TK:5096-0:871303:843082 START=05-mar-2007 \
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \
  avantd=( LK=A6F2F854633C) }
```

This example shows the `sclsort` utility sorting a license key file by using a feature name in descending order.

```
% sclsort -i in.lic -o out.lic -s feat:d
```

This example prints the following sorted license key file to the filename `out.lic`.

```
INCREMENT spice snpslmd 2010.12 30-dec-2011 1 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=184 \
SN=TK:5096-0:871303:843082 START=05-mar-2007 \
AUTH={ snpslmd=( LK=71C3F3F78009) \
sandwork=( SIGN=E3C45AB6E84E) }

INCREMENT certify snpslmd 2010.12 30-dec-2011 1 \
```

```
VENDOR_STRING=altera,xilinx \
ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \
START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCBD \
28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \
0CD1 DDE0 C9CC 7D50 56D0") }
```

```
INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
SN=TK:5096-0:871303:843082 START=05-mar-2007 \
AUTH={ snpslmd=( LK=4D45D90FAD6B) \
avantd=( LK=A6F2F854633C) }
```

---

## Using the Expiration Date in Descending Order

The following example uses the input file in.lic:

```
INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
  SN=TK:5096-0:871303:843082 START=05-mar-2007 \
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \
  avantd=( LK=A6F2F854633C) }

INCREMENT certify snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=altera,xilinx \
  ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \
  START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCBD \
  28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \
  0CD1 DDE0 C9CC 7D50 56D0") }

INCREMENT APSolar snpslmd 2010.12 30-dec-2010 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
  SN=TK:5096-0:871303:843082 START=05-mar-2007 \
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \
  avantd=( LK=A6F2F854633C) }

INCREMENT spice snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=184 \
  SN=TK:5096-0:871303:843082 START=05-mar-2007 \
  AUTH={ snpslmd=( LK=71C3F3F78009) \
  sandwork=( SIGN=E3C45AB6E84E) }
```

This example shows the `sclsort` utility sorting a license key file by using the expiration date in descending order.

```
% sclsort -p expdate:d -i in.lic -o out.lic
```

This example prints the following sorted license key file to the filename out.lic.

```
INCREMENT APSolar snpslmd 2010.12 15-nov-2011 1 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
SN=TK:5096-0:871303:843082 START=05-mar-2007 \
```

```

AUTH={ snpslmd=( LK=4D45D90FAD6B) \
avantd=( LK=A6F2F854633C) }

INCREMENT APSolar snpslmd 2010.12 30-dec-2010 1 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
SN=TK:5096-0:871303:843082 START=05-mar-2007 \
AUTH={ snpslmd=( LK=4D45D90FAD6B) \
avantd=( LK=A6F2F854633C) }

INCREMENT certify snpslmd 2010.12 30-dec-2009 1 \
VENDOR_STRING=altera,xilinx \
ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \
START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCBD \
28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \
0CD1 DDE0 C9CC 7D50 56D0") }

INCREMENT spice snpslmd 2010.12 18-nov-2009 1 \
VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=184 \
SN=TK:5096-0:871303:843082 START=05-mar-2007 \
AUTH={ snpslmd=( LK=71C3F3F78009) \
sandwork=( SIGN=E3C45AB6E84E) }

```

---

## Using the Key Name in Ascending Order and the Start Date in Descending Order

The following example uses the input file in.lic:

```

INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
  SN=TK:5096-0:871303:843082 START=05-mar-2009 \
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \
  avantd=( LK=A6F2F854633C) }

INCREMENT certify snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=altera,xilinx \
  ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \
  START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCBD \
  28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \
  0CD1 DDE0 C9CC 7D50 56D0") }

INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \
  SN=TK:5096-0:871303:843082 START=05-mar-2010 \
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \
  avantd=( LK=A6F2F854633C) }

```

The example sorts the in.lic license key file by using the key name in ascending order and the start date in descending order.

```
% sclsort -i in.lic -p feat:a -s startdate:d
```

This example prints the following sorted license key file to the filename out.lic.

```
INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \  
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \  
  SN=TK:5096-0:871303:843082 START=05-mar-2010 \  
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \  
  avantd=( LK=A6F2F854633C) }  
INCREMENT APSolar snpslmd 2010.12 30-dec-2011 1 \  
  VENDOR_STRING=^1+S SUPERSEDE ISSUED=20-apr-2007 ck=173 \  
  SN=TK:5096-0:871303:843082 START=05-mar-2009 \  
  AUTH={ snpslmd=( LK=4D45D90FAD6B) \  
  avantd=( LK=A6F2F854633C) }  
INCREMENT certify snpslmd 2010.12 30-dec-2011 1 \  
  VENDOR_STRING=altera,xilinx \  
  ISSUED=18-jun-2009 ck=222 SN=TK:255682:464396 \  
  START=18-jun-2009 AUTH={ synplctyd=( SIGN="0205 8DC3 BD05 CCB0 \  
  28A7 6940 D88A 21EA 09EE 95EF 4B03 E74F EAAA 4165 BCD6 DF4E \  
  OCD1 DDE0 C9CC 7D50 56D0") }
```



# Index

---

## C

- client and server platforms 1-3
- combined vendor daemon (*see also* snpslmd daemon, SCL) 1-2
- command usage help B-2
- commands
  - co B-4
    - options B-4
    - syntax B-4
  - lmhostid
    - purpose 9-9
    - usage 9-9
  - lmstat
    - c option 9-14
    - options 9-25
    - syntax 9-25
    - using to locate FLEXnet version 6-3
  - lmver, using to locate tool version 2-8
  - manymcoci B-6
    - options B-6
    - output report B-7
    - syntax B-6
  - mci
    - output B-5
    - syntax B-5
  - mco
    - output B-5
    - syntax B-5

- mcoci B-5
  - options B-6
  - syntax B-6
- ping -s 2-5
- ps 9-2
  - TCP-based 9-3
- compute farm 2-6
- configuration
  - lmgrd on Windows A-3
  - redundant server 2-4
  - single server 2-4
  - three-server redundancy 6-7
- counted license A-6
- CPU speed 2-3

## D

- DAEMON line 5-6
  - (*see also* VENDOR line)
  - explained 7-4
- daemons
  - legacy, failure to start 9-27
  - lmgrd 1-2, A-3
    - specifying debug log file 6-2
    - startup example 6-2
  - snpslmd 1-2, 3-2
    - behavior when server goes down 9-23
    - checking version 9-15

- combined vendor daemon 1-2
- errors 9-30, 9-31
- replacing corrupted file 9-9
- daemons,
  - egacy 1-5
- debug log file 9-2
  - checking 6-3
  - checking for SSS key errors 8-3
  - common error messages reported 9-18
  - errors 9-30
  - errors and solutions A-9
  - filtering information from 9-21
  - using to troubleshoot problems 9-17
- determining host ID 3-6
- dongle drivers
  - installing A-6
  - supported types A-5
- dongles
  - displaying the dongle ID A-3
  - locating ID on networked license A-4
  - locating ID on node-locked license A-4
  - troubleshooting A-7
  - USB application compatibility A-4

## E

- encryption key 5-7
- environment variables
  - configuring access for multiple servers 6-7
  - describing 6-4
  - FLEXNET\_DIAGNOSTICS 9-26
  - LM\_LICENSE\_FILE 3-3
  - SCL\_DAYS\_EXPIRE 8-6
  - SCL\_DISPLAY\_EXPIRE 8-6
  - SNPSLMD\_LICENSE\_FILE 3-3
  - specifying the license key file location 5-7
  - specifying values 6-5, 6-6
  - unsetting 2-6, 9-27
- error messages
  - causes 9-7
  - mapping of SCL to FLEXIm codes 9-4

- reported in debug log file 9-18
- solutions 9-8
- errors
  - in debug log file 9-30
  - Imgrd 9-30
  - multiple heartbeat checkout 9-26
  - snpslmd daemon 9-30, 9-31
  - resolution 9-31
- expiration date, license 7-6

## F

- file descriptor limit, increasing 9-29
- file system, network mounted 2-6
- FLEXID A-3
- FLEXid
  - locating ID on networked license A-4
- FLEXIm (*see* FLEXnet)
- FLEXnet
  - diagnosing problems 9-26
  - license file list behavior 3-6
  - License Finder dialog box A-11
  - LM\_LICENSE\_FILE variable 6-4
  - Imcksum 3-2
  - Imstat, locating FLEXnet version 6-3
  - Imver, locating tool version 2-8

## H

- heartbeat
  - (*see also* troubleshooting, checkout errors)
  - defined 9-26
  - minimizing errors 9-26
  - multiple failures 9-26
- host ID 7-4
  - verifying correctness 9-23
  - verifying on UNIX 5-5
  - verifying on Windows 5-5
- host name 7-4
  - argument 5-8
  - changing the default 5-8

**I****INCREMENT** line

- continuation characters 9-8
- defined 7-6
- feature version 7-6
- feature version number 7-6
- feature\_name 7-6
- SUPERSEDE keys 7-7

## installation

- directory structure 5-3
- SCL on UNIX platforms 5-1

**K**

keys, on-support A-10

**L**

## legacy Synopsys tools

- compatibility with SCL 2-8

## legacy vendor daemons 1-5

## license

- checkout errors 9-26
- denials 9-24
- dongle-based A-4
- expiration alert 8-6
- installation directory structure 5-2
- listing available licenses on Windows A-11
- monthly technology subscription 4-3
- network configurations
  - common configurations 3-3
  - multiple distributed license servers 3-4
  - single server 3-3
  - three-server redundancy 3-4
- pooling 2-2
  - and legacy daemons 2-2
  - multiple key files 9-28
  - support 2-2
- technology subscription 4-3

## license file keys

- checking out B-3

concurrent feature licenses 7-6

issued date 7-7

SSS 8-3, 9-11

SSST 9-11, 9-13

start date 7-7

License Finder dialog box A-11

## license key file

- avoiding unpredictable daemon behavior 8-2
- checking required content 9-23
- components 7-1
- debugging 9-2
- default installation directory 5-7
- defined 4-2, 7-2
- header content 7-3
- INCREMENT line 7-6
- installing 5-7
- list behavior
  - server binding 3-6
- physical location 9-14
- procedure to update 8-4
- SERVER line 7-3
- SSS security key 8-3, 9-11, 9-13
- SSST security key 9-11, 9-13
- treating as unit 5-6
- updating for overlapping keys 8-4
- USE\_SERVER line 7-5
- VENDOR line 7-4

## license keys A-6

## license server

- starting daemon 6-2
- stress testing B-5, B-6
- testing for performance B-4

## licenses

- counted A-6
- node-locked A-6

LM\_LICENSE\_FILE 3-3

lmcksum 3-2

## lmdiag

- utility 9-24
- utility, diagnosing checkout problems 9-3

## lmdiag utility

- diagnosing checkout problems 9-3
- Imdown
  - utility 5-8, 9-2
- Imgrd daemon 1-2
  - checking version 9-15
  - configuring to run as service A-3
  - errors 9-30
  - restarting 5-8
  - specifying debug log file 6-2
  - starting 6-2
  - startup example 6-2
- Imhostid 3-6
  - verifying license server host ID 5-5
- Imreread utility 3-4, 5-8
- Imstat
  - c option 9-14
  - example output 6-3
  - options 9-25
  - syntax 9-25
  - utility 9-3, 9-24
- LMTOOLS 5-1, 6-2, 6-5, A-1, A-2, A-8
- Imver utility, locating FLEXnet version 2-8
- lock files
  - removing 9-27
- log file (*see* debug log file)

**M**

- memory requirements 2-3
- Microsoft Windows (*see* Windows platforms)
- migration to SCL 2-2
- monthly technology subscription licenses 4-3
  - adding 8-2
  - defined 7-2
- MTSL revenue key 3-2
- multiple distributed servers, configuration 3-4
- multiple servers
  - configuring clients for access to 6-7

**N**

- network latency
  - ping -s command 2-5
  - value 2-5
- network mounted file system 2-6
- node-locked applications A-4
- node-locked license A-6

**O**

- on-support key A-10
- options, sysmon.sh 9-16

**P**

- ping -s command 2-5
- platform requirements, AMD64 2-3
- platforms, supported 1-3
- port@host 6-5
- port@host example usage 6-6
- ps command 9-2

**R**

- redundant server configuration 2-4
- Registry Editor, setting up service delay A-8
- revenue key
  - MTSL 3-2

**S**

- SCL
  - common problems 9-2
  - compatibility with legacy tools 2-8
  - component versions 1-2
  - components on Windows A-2
  - default installation folder A-2
  - downloading 4-2
  - environment variables 6-4
  - error conditions, possible causes 9-7

- error messages 9-29
  - migration 2-2
  - new key files, validating 8-3
  - product compatibility issues 2-8
  - shell command reference B-1
  - starting on UNIX and Windows 6-2
  - version 1-1
  - SCL shell
    - abbreviating commands and options B-3
    - command B-2
      - list 5-4
      - options B-3
    - comment character B-3
    - sclsh B-1
  - sclsh (*see also* SCL shell) 5-4
  - sclsort C-1
  - security key
    - SSS 3-2, 8-3, 9-11, 9-13
    - SSST 3-2, 9-11, 9-13
  - server
    - configurations summary 3-5
    - cross platform clients 1-3
    - selecting host 3-6
    - three-server redundancy 3-4
    - validating key B-3
  - SERVER line
    - changing on Windows A-2
    - defined 7-3
    - TCP port number 5-8
  - service delay, setting up A-8
  - settings, CP 2-5
  - single server configuration 2-4
    - defined 3-3
  - SmartKeys, logging in 4-3
  - snpslmd daemon 1-2, 3-2
    - behavior when server goes down 9-23
    - checking version 9-15
    - combined vendor daemon 1-2
    - errors 9-30, 9-31
      - resolution 9-31
    - INCREMENT line usage 7-6
    - replacing corrupted file 9-9
    - VENDOR line specification 7-5
  - SNPSLMD\_LICENSE\_FILE
    - setting for multiple single servers 3-4
    - setting for single server 3-3
    - setting for three server redundancy 3-5
  - socket descriptor limit 2-5
  - software versions, compatibility with SCL 2-8
  - SolvNet, registering for 4-2
  - SSS security key 3-2, 8-3, 9-11, 9-13
  - SSST security key 3-2, 9-11, 9-13
  - sssverify 3-2
    - error messages 9-11
    - mapping features to products 3-2
    - options 3-3
    - output 9-11
    - purpose 5-6
    - reports 9-11, 9-13
    - running 3-2, 9-11
    - syntax 3-3
  - starting SCL automatically 6-2, A-2
  - starting SCL on Windows 6-5, A-1, A-8
  - stress B-5
  - SUPERSEDE keys 7-7
  - support
    - calling 9-25
    - needed information when contacting 9-25
  - supported platforms 1-3
  - Synopsys Common Licensing, (*see* SCL)
  - Synopsys Key File sort utility C-1
  - sysmon.sh script
    - options 9-16
    - purpose 9-15
    - README.txt file 9-15
    - running 9-16
  - system monitoring script (*see* sysmon.sh script)
- ## T
- TCP 9-3

- port number 7-4
- port number error message 9-29
- settings 2-5
- technology subscription licenses
  - defined 4-3
  - retrieving 4-3
- three-server redundancy 6-2
  - configuring 6-7
  - defined 3-4
- tools, bridge 9-28
  - legacy applications 9-28
  - pooling behavior 9-28
- troubleshooting 9-1 to 9-26
  - checkout errors
    - minimizing 9-26
    - multiple heartbeat failures 9-26
  - checkout errors heartbeat (*see also* troubleshooting checkout errors) 9-26
  - dongles A-7
  - firewall problems A-10
  - heartbeat errors (*see* troubleshooting, checkout errors)
  - startup 9-2
  - Windows platforms A-10

## U

- UNIX
  - SCL installation directory 5-2
- users
  - retrieving list of 9-15
- using SCL on Windows 5-1
- Utilities
  - sclsort C-1
  - Synopsys Key File sort C-1
- utilities
  - FLEXidCLEANupUtility A-6
  - lmdiag 9-3, 9-24
  - lmdown 9-2
  - lmhostid 5-5
  - lmreread 3-4, 5-8
  - lmstat 9-3, 9-24

- lmver 2-8
- sssverify 3-2, 5-6
- whatscl 9-3, 9-14

## V

- VENDOR daemon (*see also* combined vendor daemon, snpslmd daemon) 5-8
- vendor daemons, legacy 1-5
- VENDOR line
  - changing on Windows A-2
  - defined 7-4
  - invalid daemon path 9-7
  - modifying 5-9
- version
  - FLEXnet 1-1
  - locating FLEXnet with lmstat 6-3
  - locating tool version with lmver 2-8
  - SCL 1-1

## W

- WAN
  - license checkout delays 2-6
  - license server 2-5
  - requirements for setting 2-5
- watchlog.c
  - building and running 9-21
  - monitoring debug log file for events 9-21
  - setting up 9-21
- whatscl 9-3, 9-14
- Windows platforms
  - changing SERVER line A-2
  - changing VENDOR line A-2
  - configuring lmgrd to run as service A-3
  - dongles
    - displaying dongle ID A-3
    - installing drivers A-5
    - locating ID on networked license A-4
    - locating ID on node-locked license A-4
    - troubleshooting A-7
  - USB application compatibility A-4

using on node-locked applications A-4  
License Finder dialog box A-11  
log file errors and solutions A-9  
Registry Editor A-8

SCL components for A-2  
setting license environment variables A-3  
starting SCL automatically A-2  
troubleshooting firewall problems A-10